# **PAN-TILT HEAD**

XU-80 XU-81

# PROGRAMMER'S MANUAL

Ver. 02.02

## -Contents

1. Getting	Started	5
2. Connec	ting and Setup	6
2.1	Connection	6
2.2	Connector & Pin Assignment	7
2.3	Switch Settings	7
3. Commu	nication Format	9
3.1	Signal Format	9
3.2	Understanding	9
4. Control	Command Format	10
5. Answer	Format	10
5.1	Answer Format	10
5.2	Error Code	10
5.3	Status	11
6. Classifi	cation of Command	12
6.1	Classification by Operation	12
6.2	Classification by Executive Format	12
7. Control	Command Table	14
7.1	Pan-tilt head Control Command Table	14
7.2	Camera Control Command Table	15
7.3	Camera Setting Command Table	16
7.4	System Control Command Table	17
8. Detail o	of Pan-Tilt Head Control Command	18
8.1	Pan Speed Assignment	18
8.2	Tilt Speed Assignment	19
8.3	Pan Speed Request	20
8.4	Tilt Speed Request	21
8.5	Pan Tilt Stop	22
8.6	Pan Right Start	23
8.7	Pan Left Start	24
8.8	Tilt Up Start	25
8.9	Tilt Down Start	26
8.10	Pan-Tilt Head Initialize 1	27
8.11	Pan-Tilt Head Initialize 2	28
8.12	Pan Slowest Speed Request	29
8.13	Pan Fastest Speed Request	30
8.14	Tilt Slowest Speed Request	31
8.15	Tilt Fastest Speed Request	32
8.16	Pan Angle Pulse Ratio Request	33
8.17	Tilt Angle Pulse Ratio Request	34
8.18	Pan Minimum Angle Request	35
8.19	Pan Maximum Angle Request	36
8.20	Tilt Minimum Angle Request	37
8.21	Tilt Maximum Angle Request	38
8.22	Pan/Tilt Angle Assignment	39

8.23	Pan/Tilt Angle Request	41
8.24	Wiper Control	42
8.25	Washer Control	43
8.26	Tally OFF	44
8.27	Tally ON	45
8.28	AUX OUT OFF	46
8.29	AUX OUT ON	47
8.30	AUX Status Request	48
8.31	Housing Fan Status Request	. 50
8.32	Washer Output OFF	. 52
8.33	Washer Output ON	. 53
9. Details o	f Camera Control Command	. 54
9.1	Camera Version Request	. 54
9.2	Camera OFF	. 55
9.3	Camera ON	. 56
9.4	Focus Auto	. 57
9.5	Focus Manual	. 58
9.6	Focus Fixed at Infinity	. 59
9.7	Focus Near	60
9.8	Focus Far	61
9.9	One-shot AF	62
9.10	Zoom Stop	63
9.11	Zoom Wde	64
9.12	Zoom Tele	65
9.13	Zoom Hi Wide	66
9.14	Zoom Hi Tele	67
9.15	Zoom Position Assignment	68
9.16	Zoom Position Request	69
9.17	Zoom Speed Assignment	. 70
9.18	Zoom Speed Request	. 71
9.19	Digital Zoom Magnification Assignment (XU-81)	. 72
9.20	Digital Zoom Magnification Status Request (XU-81)	. 74
749.2	1 Color Bar OFF	. 75
9.22	Color Bar ON	. 76
9.23	Color Bar Status Request	. 77
9.24	Shooting Mode Switching	. 78
9.25	Shooting Mode Status Request	. 80
9.26	Shutter Speed 1/60	. 81
9.27	Shutter Speed 1/100	
9.28	Shutter Speed Assignment	. 83
9.29	Shutter Speed Status Request	. 84
9.30	Shutter Speed Detailed Setting	. 85
9.31	Shutter Speed Detailed Status Request	
9.32	Gain Assignment	
9.33	Gain Status Request	
9.34	Gain Details Specification	

9.35	Gain Detailed Status Request	93
9.36	Iris Assignment	94
9.37	Number of Iris Divisions Request	95
9.38	Iris Position Request	96
9.39	Exposure Compensation Specification	97
9.40	White Balance Auto	98
9.41	White Balance Preset	99
9.42	White Balance Fixed 1	100
9.43	White Balance Fixed 2	101
9.44	White Balance ATW	102
9.45	White Balance Mode Status Request	103
9.46	Black Level Assignment (XU-81)	104
9.47	R Gain Assignment	105
9.48	B Gain Assignment	106
9.49	Cr Gain Assignment	117
9.50	Cb Gain Assignment	118
9.51	Edge Assignment	109
9.52	WDR OFF	110
9.53	WDR ON	121
9.54	WDR Status Request	112
9.55	ND Filter OFF	113
9.56	ND Filter ON	114
9.57	ND Filter Status Request	115
9.58	IR Filter OFF	116
9.59	IR Filter ON	117
9.60	IR Filter Status Request	118
9.61	Auto IR OFF	119
9.62	Auto IR ON (Slow Shutter)	120
9.63	Auto IR ON (Gain)	121
9.64	Auto IR Status Request	122
9.65	GENLOCK Vertical Line Information Request	123
9.66	GENLOCK Horizontal Phases Information Request	124
10. Details	of Camera Setting Command	125
10.1	AE Area Setting	125
10.2	AE Responsiveness Setting	127
10.3	AE Maximum Gain Setting	128
10.4	Brigntness Peak Compression (XU-81)	129
10.5	AF Area Setting	130
10.6	AF Sensitivity Setting	132
10.7	AWB Shift Setting	133
10.8	Gamma Level Setting	
10.9	Contrast Adjustment (XU-81)	135
10.10	TV Setup OFF	136
10.11	1 TV Setup ON	137
10.12	2 GENLOCK Phases Relative Value Adjustment	138
10.13	GENLOCK Phases Absolute Value Adjustment	139

11. Details	of System Control Command	140
11.1	Operation Status Request	140
11.2	Extended Operation Status Request	141
11.3	Product Name Request	143
11.4	ROM Version Request	144
11.5	Zoom, Focus, Tilt, and Pan Speed Control Assignment	145
11.6	Shot Memory Recording	147
11.7	Shot Memory Movement	148
11.8	Serial Number Information Request	150
12. Comma	nd Table	151

## 1. Getting Started

This manual describes commands which control the pan-tilt head system XU-80 (hereinafter XU-80) and XU-81 (hereinafter XU-81) from the host computer.

Before reading this manual, it is recommended to read Operation Manual of each product.


### CAUTION:

XU-80 and XU-81 Pan/Tilt operational durability is guaranteed for 300K cycles. In case of the continuous operation by the program such as Auto Pan Tilt System, & etc., it is important not to overdrive the said value(300K)


## 2. Connecting and Setup

## 2.1 Connection


### <RS-232 Direct Connection>



### <RS-232 Direct Connection>




## <Modem Usage >



### 2.2 Connector & Pin Assignment

### <RS-232C connection (SW1 OFF)>


Pin number	Input/Output	Signal				
2	Input	RX				
3	Output	TX				
5		GND				



RS-232C pin assignment

### <RS-422 connection (SW1 OFF)>

Pin number	Input/Output	Signal
2		GND
3	Input	RX+
4	Output	TX-
5	Output	TX+
6	Input	RX-
7		GND



RS-422 pin assignment

### 2.3 Switch Settings

The following settings are changed according to the status of the switches. Always turn off the power to the system to change the switches.

When the frame rate or video format is changed, be sure to turn the power on, confirm that the changes have been done correctly, and then turn the power off and on again before use.


SW	Description	OFF	ON
1	Communication type	RS-232C	RS-422
2	Direction of setup	Normal	Suspended
3	Frame rate	59.94	50
4	Video format	1080i	720p
5	Digital zoom operation (XU-81 only)	Optical interlocking	Independent
6	Reserve		
7	Reserve		
8	Operation mode	Standard	High speed

**Note:** XU-81 has two Digital zoom modes, which are Optical interlocking mode and Independent mode. The setting of these modes are switchable by SW5. (XU-80 has only Optical interlocking mode regardless of the setting of the switch.)

### [Optical interlocking mode]

In the field wider side than the optical telephoto end, the optical zoom works, and in the more telephoto side than the optical telephoto end, the digital zoom works. While the zooming is operated, the operation of both the optical zoom and the digital zoom interlocks in this mode.

When the zooming is operated in the optical zoom field, only the optical zoom works. When the zooming is operated toward more telephoto side than the optical telephoto end, the zooming stops once at the optical telephoto end and moves to the digital zoom field. When the zooming is operated in the digital zoom field, only the digital zoom works. When the zooming is operated the wider side than 1.0x in digital zoom magnification, the zooming moves to the optical zoom field without stop.



### [Independent mode]

The optical zoom and the digital zoom works independently. When the zooming is operated, only the optical zoom works. When the digital zooming is operated, it is necessary to use the dedicated command.

### 3. Communication Format

### 3.1 Signal Format

RS-232C and RS-422 conformity

Transmission Mode : Half Duplex
Transfer Speed : 9600 bps.
Data Bit : 8 bit
Parity : None

Parity : None Stop Bit : 1 bit Handshake : None

Others : One Acknowledge per Command

### 3.2 Understanding

Be aware the followings.

- After receiving the answer corresponding to the control command, the next control commands will be ready to transmit.
- The standard waiting time of the answer is 300 ms. If the pan-tilt head does not return the answer more than 300 ms, there must be some errors.

#### 4. Control Command Format

This format is to transmit from the computer to Pan-tilt head.

Header	Device Num	Command	Parameter	End mark
--------	------------	---------	-----------	----------

Header : 1 byte FFh Device Num : 2 byte 3030h

Command : 2 byte (refer to 8.Pan-tilt head Control Command ~ 11.System Control

**Command**)

Parameter : Variable length If not specified, Parameter manifests Hexadecimal, transmits

its ASCII code.

End mark : 1 byte EFh

#### **5. Answer Format**

### **5.1** Answer Format

This answer format corresponds to the Control Command transmitted from the computer to Pan-tilt head.

Header	Device Num	Error Code	Status	End mark	
Header	: 1 byte FEh				
Device Num	: 2 byte 3030h				
Error Code	: 2 byte manife	ested error flag I	n Hexadecimal a	and return it's AS	SCII code.
Status	: Variable length	If not specifie	ed, Status manife	ests Hexadecima	l, transmits

its ASCII code.

End mark : 1 byte EFh

#### **5.2** Error Code

Error Code manifests error flag in Hexadecimal and returns it's ASCII code. If not exists error, all bits of error flags are cleared and becomes zero.

### • The bit assignment of error flag.

b7(MSB)	b6	b5	b4	b3	b2	b1	b0(LSB)
Mode error	Parameter	Command	Busy	System	System	System	System error
Wiode ciroi	error	error	Dusy	reservation	reservation	reservation	System enor

1st byte	b/: Mode Error	In case of wrong mode
	b6: Parameter Error	In case of receiving wrong parameter
	b5: Command Error	In case of receiving wrong command
	b4: Busy	In case of unable to execute by error
2nd byte	b3: System Reservation	Always Zero
	b2: System Reservation	Always zero
	b1: System Reservation	Always Zero
	b0: System Error	In case of the fatal error to the system

The details of Error Flags are described as below.

Busy : Pan-tilt head is unable to execute the commands in process to execute the

former command.

: In case of generating Command Error, Parameter Error, Mode Error or

System Error.

Command Error : In case of receiving the wrong commands (not prepared commands)

Parameter Error : In case of over value of parameter or wrong parameter length.

Mode Error : In case of receiving the command unable to execute under Pan-tilt head

during the receiving Status.

System Error : In case that the fatal accidents occur for some reason.

### **CAUTION**

• By **Operation Status Request**, the cause of error can be found.

• The error check will be executed by the following priority order.

(1) Command Error

(2) Mode Error, Busy

(3) Parameter Error

Pan-tilt head sets the error flag corresponding to any, after the detection of error, and returns the answer, then multiple error flags can't be set. Busy, however, is exceptional and set, whenever any of Command Error, Parameter Error, Mode Error or System Error occurs.

Example: Wrong command to be transmitted.

Note: When the Command errors occur and unable to execute, Busy flag and command error flag will be set at the 1.

#### 5.3 Status

In case of having received Status Request Command, this status adds status value to the answer. The details of **Operation Status Request** command and status value are described later. (Refer to **11. Details of System Control Command**)

#### 6. Classification of Command

### 6.1 Classification by Operation

"Pan-tilt head" consists of pan-tilt head and camera sections, and command consists of Pan-tilt head control, camera control, camera setting, and system control. This manual describes according to this classification.

#### (I) Pan-tilt head Control

This control is to inquire and to indicate operation for pan-tilt head.

Pan Speed Assignment, Pan Speed Request, Pan Angle Request, etc. are counted among this classification. See the Table 7.1 Pan-tilt head Commands, and 8. Details of Pan-tilt head Control Commands.

#### (II) Camera Control

This control is to set each parameter, to inquire and to indicate operation for camera.

Zoom Speed Assignment, Zoom Position Request, Zoom Position Assignment, etc. are counted among this classification.

See the Table 7.2 Camera Control Command and 9. Details of Camera Control Commands.

### (III) Camera Settings

This sets various camera parameters. Commands for **AE** area setting and **GENLOCK** phase relative value adjustments belong to this class. Parameters set by this class of commands are saved in the camera's memory, and are retained even when the camera is powered off. For that reason, there is no need to reset them after a system reset and the like, once they have been set during setup. Do not operate anything other than the camera settings for three seconds after making these settings. See section **7.3** System Control Command Table for a list of commands, and Chapter **10** Details of System Control Command for details on the commands.

### (IV) System Control

This control is to Operation of Both Camera and Pan-tilt head, to inquire the Inside status and etc. **Status Request of Operation** is counted among this classification.

See the Table 7.4 System Control Command and 11. Details of System Control Commands.

### **6.2** Classification by Executive Format

Each command classify as one of Synchronous Execution (type 1) and other of Non-Synchronous Execution (type 2)

### (I) Synchronous Execution (type 1)


This command executes immediately at the time of Command receipt, and complete the execution at the time of the answer completed.

The command among this classification enable to accept the next command at the moment of Answer transmission. This classified commands describe in **8. Detail of Pan-tilt head Control** ~

#### 11. Camera Control Commands as type 1.

Timing diagram describes below.

The answering time after receipt of the command code is 10 ms in Standard, and 30 ms Max. And the execution completes at the beginning of transmission




### (II) Non-Synchronous Execution A (type 2)

On receipt of the command code, this command transmits the command without waiting of the completion to execute. The completion of operation can be found by the status of flag among the operation status.

The commands classified in this, describe in **8. Details for Pan-tilt head Control Command** ~ **11. System Control Command as type 2**.

Timing diagram of the operation describes below.

The answering time after receipt of the command code, is 10 ms Standard, 30 ms Max The time between start and stop, is depend on the class of commands and condition to be executed.



### 7. Control Command Table

## 7.1 Pan-tilt head Control Command Table

Function	Meaning	Command	Parameter	Status
Pan Speed Assignment	Set the running speed for panning	0150h	005h to 7D0h	None
Tilt Speed Assignment	Set the running speed for tilting	0151h	005h to 7D0h	None
Pan Speed Request	Return the present running speed for panning	0152h	0h	005h to 7D0h
Tilt Speed Request	Return the present running speed for tilting	0152h	1h	005h to 7D0h
Pan Tilt Stop	Stop the panning/tilting operations	0153h	0h	None
Pan Right Start	Start panning to right	0153h	1h	None
Pan Left Start	Start panning to left	0153h	2h	None
Tilt Up Start	Start tilting upward	0153h	3h	None
Tilt Down Start	Start tilting downward	0153h	4h	None
Pan-Tilt Head Initialize 1	Move home position after initialization	0158h	0h	None
Pan-Tilt Head Initialize 2	Move to the original position after initialization	0158h	1h	None
Pan Slowest Speed Request	Return the slowest speed for panning	0159h	0h	005h
Pan Fastest Speed Request	Return the fastest speed for panning	0159h	1h	7D0h
Tilt Slowest Speed request	Return the slowest speed for tilting	0159h	2h	005h
Tilt Fastest Speed request	Return the fastest speed for tilting	0159h	3h	7D0h
Pan Angle Pulse Ratio Request	Return the coefficient of pan- angle conversion	015Bh	0h	07D0h
Tilt Angle Pulse Ratio Request	Return the coefficient of tilt-angle conversion	015Bh	1h	07D0h
Pan Minimum Angle Request	Return the minimum angle of panning	015Ch	0h	5CD8h
Pan Maximum Angle Request	Return the maximum angle of panning	015Ch	1h	A328h
Tilt Minimum Angle Request	Return the minimum angle of tilting	015Ch	2h	669Ch
Tilt Maximum Angle Request	Return the maximum angle of tilting	015Ch	3h	9964h
Pan/Tilt Angle Assignment	Move to assigned position of panning/tilting	0162h	XXXX, YYYYh	None
Pan/Tilt Angle Request	Return the present position of panning/tilting	0163h	None	XXXX, YYYYh
Wiper Control	Operate the wiper	017Ah	0h	None
Washer Control	Control the washer	017Ah	1h	None
Tally OFF	Turn off tally	017Bh	0h	None
Tally ON	Turns on tally	017Bh	1h	None
AUX OFF	Turn AUX output terminal off	0171h	0h, 0h	None
AUX ON	Turn on the AUX output terminal	0171h	0h, 1h	None
AUX Status Request	Request the AUX status	01EAh	Ah	aa
Housing Fan Status Request	Request the housing fan status	01EAh	Ah	bb
Washer output OFF	Turn off the washer output	0171h	Bh, 0h	None
Washer output ON	Turn on the washer output	0171h	Bh, 1h	None

Note: The values in the parameter and status columns are examples of operation modes (standard settings). XXXX, YYYY means Pan angle, Tilt angle In Hexadecimal. "aa" is hexadecimal indicating the AUX status. "bb" is hexadecimal indicating the status of the housing fan.

## 7.2 Camera Control Command Table

Function	Meaning	Command	Parameter	Status
Camera Version Request	Request the camera version	01BEh	0h	01h
Camera OFF	Turn off the power for camera section	01A0h	0h	None
Camera ON	Turn on the power for camera section	01A0h	1h	None
Focus Auto	Change the mode of focus to AF	01A1h	0h	None
Focus Manual	Stop and change of focus to Manual	01A1h	1h	None
Focus Fixed at Infinity	Fix the focus to infinity.	01A1h	Bh	None
Focus Near	Move to near focus	01A1h	2h	None
Focus Far	Move to far focus	01A1h	3h	None
Focus One-shot AF	Perform the one-shot AF	01A1h	Ah	None
Zoom Stop	Stop zoom operation	01A2h	0h	None
Zoom Wide	Zoom to wide side	01A2h	1h	None
Zoom Tele	Zoom to telephoto side	01A2h	2h	None
Zoom Hi Wide	Zoom to wide side in high speed	01A2h	3h	None
Zoom Hi Tele	Zoom to telephoto side in high speed	01A2h	4h	None
Zoom Position Assignment	Move to the assigned zoom position	01A3h	00h to EEh	None
Zoom Position Request	Return the present zoom position	01A4h	None	00h to EEh
Zoom Speed Assignment	Assign the running speed of zooming	01B4h	1h, 0h to 7h	None
Zoom Speed Request	Return the present running speed	01B4h	2h	0h to 7h
Digital Zoom Magnification Assignment	Specify the digital zoom magnification	01DAh	00h to 6Eh	None
Digital Zoom Magnification Status Request	Request the digital zoom magnification information	01C6h	Ah	00h to 6Eh
Color BAR OFF	Turn off the color bar output and switch the output video to camera video	01B8h	Oh	None
Color BAR ON	Switch the output video to color bars	01B8h	1h	None
Color BAR Status Request	Request the color bar status information	01C5h	2h	0h, 1h
Shooting Mode Switching	Switch the camera shooting mode	0184h	0h to 4h	None
Shooting Mode Status Request	Request the shooting mode status information	01C5h	3h	0h to 4h
Shutter Speed 1/60 (PAL:1/50)	Change the shutter speed to 1/60 (PAL:1/50)	01A8h	1h	None
Shutter Speed1/100	Change the shutter speed to 1/100	01A8h	2h	None
Shutter Speed Assignment	Set the shutter speed	01ADh	0h to 4h	None
Shutter Speed Status Request	Request the shutter speed status information	01C5h	5h	0h to 4h
Shutter Speed Detailed Settings	Set the shutter speed	019Dh	79h to 8Fh	None
Shutter Speed Status Request	Request the shutter speed status information	01C6h	1h	79h to 8Fh
Gain Assignment	Assign the camera gain	01AEh	0h to 5h	None
Gain Status Request	Request the gain status information	01C5h	4h	0h to 5h
Gain Details Specification	Set the camera gain	019Eh	XU-80: 00h to 10h XU-81: 00h to 15h	None
Gain Details Status Request	Request the camera gain status information	01C6h	0h	XU-80: 00h to 10h XU-81: 00h to 15h
Iris Assignment	Assign the iris position	01A6h	00h to FFh	None
Number of Iris Divisions Request	Return the number of iris divisions	01C3h	1h	XU-80: 15h XU-81: 11h

				XU-80:
Iris Position Request	Return the current iris positions	01C3h	2h	00h to 14h XU-81: 00h to 10h
Exposure Compensation Specification	Compensate the exposure	01E3h	00h to FFh	None
White Balance Auto	Set the white balance to auto	01A7h	0h	None
White Balance Preset	Preset the white balance	01A7h	1h	None
White Balance Fixed 1	Set the white balance to indoor setting level	01A7h	2h	None
White Balance Fixed 2	Set the white balance to outdoor setting level	01A7h	3h	None
White Balance ATW	Set the white balance to ATW	01A7h	4h	None
White Balance Status Request	Request the white balance status information	01C5h	8h	0h to 4h
Black Level Assignment	Set the black level	01E1h	0h, 00h to FFh	None
R Gain Assignment	Set R gain	01E1h	1h, 00h to FFh	None
B Gain Assignment	Set B gain	01E1h	3h, 00h to FFh	None
Cr Gain Assignment	Set the Cr gain	01E1h	4h, 00h to FFh	None
Cb Gain Assignment	Set the Cb gain	01E1h	6h, 00h to FFh	None
Edge Assignment	Set the edge	01E1h	Ah, 00h to FFh	None
WDR OFF	Turn off the wide dynamic range	01A5h	0h	None
WDR ON	Turn on the wide dynamic range	01A5h	1h	None
WDR Status Request	Request the wide dynamic range status information	01C5h	7h	0h, 1h
ND filter OFF	Turn off the ND filter	01B6h	0h	None
ND filter ON	Turn on the ND filter	01B6h	1h	None
ND filter Status Request	Request the ND filter status information	01C5h	0h	0h, 1h, Fh
IR filter OFF	Turn off the IR filter	01BBh	0h	None
IR filter ON	Turn on the IR filter	01BBh	1h	None
IR filter Status Request	Request the IR filter status information	01C5h	Bh	0h, 1h
Auto IR OFF	Turn off the auto IR	01BAh	0h	None
Auto IR ON (shutter)	Turn on the auto IR (shutter)	01BAh	1h	None
Auto IR OFF (gain)	Turn on the auto IR (gain)	01BAh	2h None	
Auto IR Status Request	Request the auto IR status information	01C5h	Ah	0h to 2h
GENLOCK Vertical Line Information Request	Request the GENLOCK vertical line information	01C7h	0h	0000h to 000Fh
GENLOCK Horizontal Phases Information Request	Request the GENLOCK horizontal phases information	01C7h	1h	0000h to 0897h

## 7.3 Camera Setting Command Table

Function	Meaning	Command	Parameter	Status
AE Area Setting	Set the AE area	01BDh	1h, 0h to Bh	None
AE Responsiveness Setting	Set the AE responsiveness	01BDh	2h, 0h to 2h	None
AE Maximum Gain Setting	Set the AE maximum gain	01BDh	3h, XU-80: 0h to 7h XU-81: 0h to 9h	None
Brightness Peak Compression Assignment	Assign the brightness peak compression rate	01F0h	1h, 00h to 10h	None
AF Area Setting	Set the AF area	01BDh	4h, 0h to Bh	None
AF Sensitivity Setting	Set the AF sensitivity	01BDh	5h, 0h to 1h	None
AWB Shift Setting	Set the AWB shift	01BDh	6h, 0h to 6h	None

Gamma Level Setting	To set the gamma level	01F2h	XU-80: 0h to4h XU-81: 0h to 5h	None
TV Setup OFF	To turn the TV setup off	01E1h	Bh, 0h, 0h	None
TV Setup ON	Turns the TV Setup on	01E1h	Bh, 0h, 1h	None
GENLOCK Phases Relative Value Adjustment	Adjusts GENLOCK to the relative value.	01E4h	00h to FFh	None
GENLOCK Phases Absolute Value Adjustment	Adjusts GENLOCK to the absolute value.	01E7h	0000h to 000Fh 0000h to 0897h	None

## 7.4 System Control Command Table

Function	Meaning	Command	Parameter	Status
Operation Status Request	Return the operation status	0186h	None	3 byte
Extended Operation Status Request	Return the extended operation status	0186h	0h	5 byte
Product Name Request	Return the product name	0187h	None	"XU-80"
ROM Version Request	Return ROM version of pan-tilt head	0188h	None	"V01-01"
Zoom, Focus, Tilt, Pan Speed Control	Operate at the assigned zooming, focusing, tilting, and panning speeds.	0181h	00h to 7Fh	None
Shot Memory Recording	Record the present position to the shot memory.	0182h	00h to 1Fh	None
Shot Memory Movement	Move to the specified shot memory number position.	0183h	00h to 7h 00h, 02h to 30h	None
Serial Number Status Request	Request the serial number information	01E9h	0h	15 byte

Note: The values in the parameter and status columns of GENLOCK are examples for videos (at the frame rate of 59.94 and the video format of 1080i).

## 8. Detail of Pan-Tilt Head Control Command

## 8.1 Pan Speed Assignment

## Pan-Tilt Head Control Command Type 1

Function	Set the running	Set the running speed for panning				
Command	0150h					
Parameter	Length	3 byte				
	Range	Standard mode: 5 to 2000 (005h to 7D0h)				
		High speed mode: 5 to 3000 (005h to BB8h)				
	Default Value	Standard mode: 2000 (7D0h)				
		High speed mode: 3000 (BB8h)				
Status	None					
Reference	• 1LSB of parar	neter value is equal to 0.02 degree/s.				
	Commands with the command	• Commands which speed setting is enabled by this command are <b>Pan Right</b>				
	Start and Pan Left Start, total 2 commands.					
	• After this command is issued, issuing a command of <b>Pan Right Start</b> or <b>Pan</b>					
	Left Start ena	bles to pan at assigned speed.				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand		Parameter	•	End mark
FFh	30h	30h	01h	50h	p0	p1	p2	EFh
				.11.				

The running speed indicates in Hexadecimal 3 digits, and its ASCII code treats as							
parameter.							
example:					p0	p1	p2
	150	$\Rightarrow$	096h	$\Rightarrow$	30h	39h	36h

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FFh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example					e0 e1	
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

Parameter Error	•Assigned parameter is an invalid value.

### 8.2 Tilt Speed Assignment

### Pan-Tilt Head Control Command Type 1

Function	Set the running speed for tilting					
Command	0151h					
Parameter	Length	3 byte				
	Range	Standard mode: 5 to 2000 (005h to 7D0h)				
		High speed mode: 5 to 3000 (005h to BB8h)				
	Default Value	Standard mode: 2000 (7D0h)				
		High speed mode: 3000 (BB8h)				
Status	None					
Reference	• 1LSB of paran	neter value is equal to 0.02 degree/s.				
	• Commands wh	• Commands which speed setting is enabled by this command are <b>Tilt Down</b>				
	Start and Tilt Up Start, total 2 commands.					
	• After this command is issued, issuing a command of <b>Tilt Down Start</b> or <b>Tilt</b>					
	Up Start enab	oles to tilt at assigned speed.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	Device Num Command		Parameter			End mark	
FFh	30h	30h	01h	51h	p0	p1	p2	EFh
11								

The running speed indicates in 3-digit Hexadecimal, and its ASCII code treats as parameter.

example: p0 p1 p2 p2 p350 p350 p350 p350 p450

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FFh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example e0 e1

■ In case of No Error : 00000000B ⇒ 00h ⇒ 30h 30h

■ In case of Parameter Error : 01010000B ⇒ 50h ⇒ 35h 30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.3 Pan Speed Request

## Pan-Tilt Head Control Command Type 1

Function	Request the run	Request the running speed for panning			
Command	0152h				
Parameter	Length	1 byte			
	Value	0h			
Status	Length	3 byte			
	Range	Standard mode: 5 to 2000 (005h to 7D0h)			
		High speed mode: 5 to 3000 (005h to BB8h)			
Reference	•1 LSB of Status value is equal to 0.02 degree/s				

### • Format of Control Code

	10	d1	d2	d3	d4	d5	d6
He	ader	Device Num		Command		Parameter	End mark
F	Fh	30h	30h	01h	52h	30h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8
header	Device	e Num	Error Code		Status			End mark
FEh	30h	30h	30h	30h	s0	s1	s2	EFh
<b>U</b>								

The running speed indicates in 3-digit Hexadecimal, and its ASCII code treats as							
status.							
example:					s0	s1	s2
	150	$\Rightarrow$	096h	$\Rightarrow$	30h	39h	36h

## ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example	e0 e1					
■ In case of Parameter Error :	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$					

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

### **8.4** Tilt Speed Request

### Pan-Tilt Head Control Command Type 1

Function	Request the runi	Request the running speed for tilting				
Command	0152h	0152h				
Parameter	Length 1 byte					
	Value	1h				
Status	Length	3 byte				
	Range	Standard mode: 5 to 2000 (005h to 7D0h)				
		High speed mode: 5 to 3000 (005h to BB8h)				
Reference	•1 LSB of Status value is equal to 0.02 degree/s					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	52h	31h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8
header	Device	e Num	Com	mand		Status		End mark
FEh	30h	30h	30h	30h	s0	s1	s2	EFh
				- II				

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				- III	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example:

e0 e1

In case of Parameter Error: 01010000B ⇒ 50h ⇒ 35h 30h

### • Condition of Error flag to be set

Parameter Error •Assigned parameter is an invalid value.

## 8.5 Pan Tilt Stop

## Pan-Tilt Head Control Command Type 2

Function	Stop the pann	Stop the panning/tilting operations			
Command	0153h	0153h			
Parameter	Length	Length 1 byte			
	Value	0h			
Status	None				
Reference					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	53h	30h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
EFh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example

In case of No Error:

00000000B ⇒ 00h ⇒ 30h 30h

In case of Parameter Error:

01010000B ⇒ 50h ⇒ 35h 30h

Parameter Error • Assigned parameter is an invalid value.
-----------------------------------------------------------

## 8.6 Pan Right Start

Tilt Head Control Command Type 2

Function	Start panning to right						
Command	0153h						
Parameter	Length 1 byte						
	Value	1h					
Status	None						
Reference	•Until <b>Pan Tilt Stop</b> command issues, or right limit position, continue to run.						
	•The running speed is able to set by <b>Pan Speed Assignment</b> command.						
	•By issuing this command, 1 is set in <b>Panning flag</b> among the Operating						
	Status.	Status.					
	The setting flag will be done, just before running Pan-tilt head. When Pan-tilt						
	head reaches to the right limit, Pan running will stop and clear <b>Panning flag</b>						
	to 0.						
	•While panning in the right direction by this command, it is able to						
	compulsory sto	op operation by Pan Left Start command.					

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	53h	31h	EFh


## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
EFh	30h	30h	e0	e1	EFh
				<u>Il</u>	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value					
Example	e0 e1				
■ In case of No Error:	$00000000B \Rightarrow 00h \Rightarrow 30h 30h$				
■ In case of Busy:	$00010000B \Rightarrow 10h \Rightarrow 31h 30h$				
■ In case of Parameter Error :	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$				

### • Condition of Error flag to be set

Condition of End.	1100 10 00 00
Busy	•While executing <b>Shot Memory Movement</b> and <b>Pan Tilt Angle</b>
	Assignment commands.
	•While executing Wiper Control and Washer Control
	commands.
	•While executing <b>ND Filter Control</b> commands.
Parameter Error	•Assigned parameter is an invalid value.



Normal Mounting: Right direction

### 8.7 Pan Left Start

### Pan-Tilt Head Control Command Type 2

Function	Start panning to left				
Command	0153h				
Parameter	Length	1 byte			
	Value	2h			
Status	None				
Reference	•Until Pan/Tilt Stop Command issues, or reaches to the left limit, continue to				
	run.				
	•The running speed cab be set by <b>Pan Speed Assignment</b> command.				
	•By issuing this command, 1 is set in <b>Panning flag</b> among the Operating				
	status.				
	The setting flag will be done, just before running Pan-tilt head. When Pan-tilt				
	head reaches to the left limit, Pan running will stop and clear <b>Panning flag</b> .				
	•While panning in the left direction by this command, it is able to				
	compulsory sto	op operation by Pan Right Start command.			

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h	30h	01h	53h	32h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	Code	End mark
EFh	30h	30h	e0	e1	EFh
				Ш	


Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example

In case of No Error:  $00000000B \Rightarrow 00h \Rightarrow 30h 30h$ In case of Busy:  $00010000B \Rightarrow 10h \Rightarrow 31h 30h$ In case of Parameter Error:  $01010000B \Rightarrow 50h \Rightarrow 35h 30h$ 

### • Condition of Error flag to be set

Busy	•While executing Shot Memory Movement and Pan Tilt Angle
	Assignment commands.
	•While executing Wiper Control and Washer Control
	commands.
	•While executing <b>ND Filter Control</b> commands.
Parameter Error	•Assigned parameter is an invalid value.



Normal Mounting: Left direction

## 8.8 Tilt Up Start

## Pan-Tilt Head Control Command Type 2

Function	function Start tilting upward						
Command	0153h						
Parameter	Length	1 byte					
	Value	3h					
Status	None						
Reference	<ul> <li>•Until Pan/Tilt Stop command issues, or reaches to the upper limit, continue to run.</li> <li>•The running speed is able to set by Tilt Speed Assignment command.</li> </ul>						
	•By issuing this command, 1 is set in <b>Tilting flag</b> among the Operating status.						
	<ul> <li>The setting flag will be done, just before running pan-tilt head. When pan-tilt head reaches to the upper limit, Tilt running will stop and clear <b>Tilting flag</b> to 0.</li> <li>While tilting to the UP by this command, it is able to compulsory stop</li> </ul>						
	operation by <b>Tilt Down Start</b> command.						

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h	30h	01h	53h	33h	EFh


## • Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	Code	End mark
EFh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example					e0 e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Busy:	00010000B	$\Rightarrow$	10h	$\Rightarrow$	31h 30h		
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		

## • Condition of Error flag to be set

Busy	•While executing Shot Memory Movement and Pan Tilt Angle
	Assignment commands.
	•While executing Wiper Control and Washer Control
	commands.
	•While executing <b>ND Filter Control</b> commands.
Parameter Error	•Assigned parameter is an invalid value.



Normal Mounting: Up direction

### 8.9 Tilt Down Start

## Pan-Tilt Head Control Command Type 2

Function	nward					
Command	0153h					
Parameter	ameter Length 1 byte					
	Value	4h				
Status	None					
Reference	•Until Pan/Tilt	<b>Stop</b> Command issues, or reaches to the lower limit, continue				
	to run.					
	•The running sp	eed is able to set by <b>Tilt Speed Assignment</b> command.				
	•By issuing this	command, 1 is set in <b>Tilting flag</b> among the Operating				
	status.					
	The setting flag	g will be done, just before running Pan-tilt head. When Pan-tilt				
	head reaches to	o the low limit, Tilt running will stop and clear <b>Tilting flag</b> .				
	•While tilting to	the Down by this command, it is able to compulsory stop				
	operation by <b>Tilt Up Start</b> command.					

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h	30h	01h	53h	34h	EFh


### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	Code	End mark
EFh	30h	30h	e0	e1	EFh
				][	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example					e0 e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Busy:	00010000B	$\Rightarrow$	10h	$\Rightarrow$	31h 30h		
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		

## • Condition of Error flag to be set

Condition of End.	20110111011 01 21101 11105 10 00 000					
Busy	•While executing <b>Shot Memory Movement</b> and <b>Pan Tilt Angle</b>					
	Assignment commands.					
	•While executing Wiper Control and Washer Control					
	commands.					
	•While executing <b>ND Filter Control</b> commands.					
Parameter Error	•Assigned parameter is an invalid value.					



Normal Mounting: Down direction

### 8.10 Pan-Tilt Head Initialize 1

## Pan-Tilt Head Control Command Type 2

Function	Move home position after initialization of pan-tilt head					
Command	0158h					
Parameter	Length	1 byte				
	Value	0h				
Status	None					
Reference	•After initializat	ion, run to Home Position. (Pan: Front side; Tilt: Horizontal)				
	•Home Position	(Front) is originally set at the following position.				
	Angle of F	an direction(position) 0 degree (8000h)				
	Angle of T	ilt direction(position) normal -90 degrees (6E6Ch)				
	suspended 90 degrees (9194h)					
	•The camera section is reset by executing this command.					
	•Communication	n not possible while this command is executing. No control				
	commands are	received in this state.				

### • Format of Control Code

d0	d1 d2		d3 d4		d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h 30h		58h	30h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				- II	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example

In case of No Error:

00000000B ⇒ 00h ⇒ 30h 30h

In case of Parameter Error:

01010000B ⇒ 50h ⇒ 35h 30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

### 8.11 Pan-Tilt Head Initialize 2

### Pan-Tilt Head Control Command Type 2

Function	Move to the original position after initialization of pan-tilt head					
Command	0158h	0158h				
Parameter	Length 1 byte					
	Value 1h					
Status	None					
Reference	•After initializa	tion, runs to former position.				
	•The camera sec	•The camera section is reset by executing this command.				
	<ul> <li>Communicatio</li> </ul>	•Communication not possible while this command is executing. No control				
	commands are	received in this state.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	58h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value

Example e0 e1

■ In case of No Error: 00000000B ⇒ 00h ⇒ 30h 30h

■ In case of Parameter Error: 01010000B ⇒ 50h ⇒ 35h 30h

Parameter Error	•Assigned parameter is an invalid value.	
-----------------	------------------------------------------	--

## 8.12 Pan Slowest Speed Request

## Pan-Tilt Head Control Command Type 1

		<u> </u>				
Function	Return the slowest running speed for panning					
Command	0159h	0159h				
Parameter	Length	1 byte				
	Value	0h				
Status	Length	3 byte				
	Value	5 (005h)				
Reference	•To return the sl	owest speed enable to set the running speed of Pan direction				
	by Pan Speed Assignment command.					
	•The status value	•The status value 5 is equal to approx. 0.1 degrees/s.				

### • Format of Control Code

d0	d1 d2		d0 d1 d2 d3 d4		d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	59h	30h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8
header	Device Num		Error Code		Status			End mark
FEh	30h	30h	30h	30h	30h	30h	35h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example				e0 e1			
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h =	$\Rightarrow$ 35h 30h			

Parameter Error	•Assigned parameter is an invalid value.
rafailletel Elloi	Assigned parameter is an invalid value.

## 8.13 Pan Fastest Speed Request

## Pan-Tilt Head Control Command Type 1

Function	Return the faste	Return the fastest running speed for panning				
Command	0159h					
Parameter	Length 1 byte					
	Value	1h				
Status	Length	3 byte				
	Value	Standard mode: 2000 (7D0h)				
		High speed mode: 3000 (BB8h)				
Reference	•To return the fa	astest speed enable to set the running speed of Pan direction				
	by Pan Speed	Assignment command.				
	•The status valu	e 2000 is equal to approx. 40 degree/s.				
	•The status value 3000 is equal to approx. 60 degree/s.					

### • Format of Control Code

d0	d1 d2		d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h 30h		01h	59h	31h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8
header	Device Num		Error Code		Status			End mark
FEh	30h	30h	30h	30h	42h	42h	38h	EFh

### ■ In case of Error

d0	dl	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example					e0 e1		
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.14 Tilt Slowest Speed Request

## Pan-Tilt Head Control Command Type 1

Function	Return the slowest running speed for tilting					
Command	0159h					
Parameter	Length 1 byte					
	Value 2h					
Status	Length	3 byte				
	Value	5 (005h)				
Reference	•To return the sl	lowest speed enable to set the running speed of Tilt direction				
	by <b>Tilt Speed</b>	by Tilt Speed Assignment command.				
	•The status value 5 is equal to approx. 0.1 degrees/s.					

### • Format of Control Code

d0	d1	d1 d2		d4	d5	d6
Header	Devic	Device Num		Command		End mark
FFh	30h	30h 30h		59h	32h	EFh

### Answer Format

### ■ In case of no Error

_	d0	d1	d2	d3	d4	d5	d6	d7	d8
	header	Device Num		Error Code		Status			End mark
	FEh	30h	30h	30h	30h	30h	30h	35h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example	e0 e1						
■ In case of Parameter Error :	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$						

Parameter Error	•Assigned parameter is an invalid value.
rafailletel Elloi	Assigned parameter is an invalid value.

# 8.15 Tilt Fastest Speed Request

## Pan-Tilt Head Control Command Type 1

Function	Return the fast	Return the fastest running speed for tilting					
Command	0159h	0159h					
Parameter	Length	1 byte					
	Value	3h					
Status	Length	3 byte					
	Value	Standard mode: 2000 (7D0h)					
		High speed mode: 3000 (BB8h)					
Reference	•To return the	fastest speed enable to set the running speed of Tilt direction					
	by Tilt Speed Assignment command.						
	•The status value 2000 is equal to approx. 40 degrees/s.						
	•The status value 3000 is equal to approx. 60 degrees/s.						

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h 30h		01h	59h	33h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device Num		Error Code		Status			End mark
FEh	30h	30h	30h	30h	42h	42h	38h	EFh

## ■ In case of Error

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h	30h	e0 e1		EFh	
				П		

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example	e0 e1						
■ In case of Parameter Error :	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$						

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.16 Pan Angle Pulse Ratio Request

## Pan-Tilt Head Control Command Type 1

Function	Return the coefficient to convert the parameter value or the status value used						
	for <b>Pan angle</b> (p	for Pan angle(position) and Pan speed commands to angle unit					
Command	015Bh	015Bh					
Parameter	Length	1 byte					
	Value	0h					
Status	Length 4 byte						
	Value	2000 (07D0h)					
Reference	•To return integral value multiplied 100,000 to the conversion coefficient of true Pan angle. In case of angle conversion, divide it by 100,000 Example below, Status value /100,000 = 2000 /100,000 = 0.02						
	Example: The parameter of <b>Pan Speed Assignment</b> command can be converted as under.  Pan speed $(3000) \Rightarrow 3000 \times 0.02 = 60$ degrees/s						

## • Format of Control Code

	d0	d1	d2	d3	d4	d5	d6
	Header	Device Num		Command		Parameter	End mark
Ī	FFh	30h	30h	01h	5Bh	30h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
header	Device Num		Error Code		Status				End mark
FEh	30h	30h	30h	30h	30h	37h	44h	30h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h	30h 30h		e1	EFh	
				Ш		

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example	e0 e1						
■ In case of Parameter Error :	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$						

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.17 Tilt Angle Pulse Ratio Request

## Pan-Tilt Head Control Command Type 1

Function	Return the coefficient to convert the parameter value or the status value used						
	for <b>Tilt angle</b> (	for <b>Tilt angle</b> (position) and <b>Tilt speed</b> commands to angle unit					
Command	015Bh						
Parameter	Length	1 byte					
	Value	1h					
Status	Length	4 byte					
	Value	2000 (07D0h)					
Reference		gral value multiplied 100,000 to the conversion coefficient of e. In case of angle conversion, divide it by 100,000. Example					
	Sta	atus value $/100,000 = 2000 /100,000 = 0.02$					
	Example: The	parameter of Tilt Speed Assignment command can be					
	converted as under.						
	Til	t speed (3000) $\Rightarrow$ 3000 $\times$ 0.02 = 60 degrees/s					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	Command		End mark
FFh	30h 30h		01h 5Bh		31h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
header	Devic	e Num	um Error Code		Status				End mark
FEh	30h	30h	30h	30h	30h	37h	44h	30h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				П	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value							
Example			e0 e1				
■ In case of Parameter Error :	01010000B =	$\Rightarrow$ 50h $\Rightarrow$	35h 30h				

Parameter Error	•Assigned parameter is an invalid value.

## 8.18 Pan Minimum Angle Request

## Pan-Tilt Head Control Command Type 1

		V 1					
Function	Return the min	Return the minimum value (left end) for panning angle (position)					
Command	015Ch	015Ch					
Parameter	Length	1 byte					
	Value	0h					
Status	Length	4 byte					
	Value	-9000 (5CD8h)					
Reference	•Status Value (	•Status Value (-9000) is the position rotated approx. 180 degrees to left as					
	zero degree for front.						

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h 30h		01h	5Ch	30h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
Header	Device	e Num	Error	Code	Status				End mark
FEh	30h	30h	30h	30h	35h	43h	44h	38h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

	•				
Error Flag indicates in Hexadecimal 2 digits and returns ASCII value					
Example			e0 e1		
■ In case of Parameter Error :	01010000B	$\Rightarrow$ 50h $\Rightarrow$	35h 30h		

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.19 Pan Maximum Angle Request

## Pan-Tilt Head Control Command Type 1

Function	Return the maxi	Return the maximum value (right end) for panning angle (position)					
Command	015Ch	15Ch					
Parameter	Length	Length 1 byte					
	Value	1h					
Status	Length	Length 4 byte					
	Value	9000 (A328h)					
Reference	•Status Value (+9000) is the position rotated approx. 180 degrees to right as						
	zero degree for front.						

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h	30h	01h	5Ch	31h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
Header	Device	e Num	Error	Code		Sta	tus		End mark
FEh	30h	30h	30h	30h	41h	33h	32h	38h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h 30h		e0	e1	EFh

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example					e0 e1	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

Darameter Error	•Assigned parameter is an invalid value.
I arameter Error	Assigned parameter is an invalid value.

## 8.20 Tilt Minimum Angle Request

# Pan-Tilt Head Control Command Type 1

Function	Return the mini	Return the minimum value (down end) for tilting angle (position)					
Command	015Ch	15Ch					
Parameter	Length	ength 1 byte					
	Value	2h					
Status	Length	Length 4 byte					
	Value	-6500 (669Ch)					
Reference	,	•Status Value(-6500) is the position rotated approx. 130 degrees to down as zero degree for horizontal.					

## • Format of Control Code

	d0	d1	d2	d3	d4	d5	d6
Н	Ieader	er Device Num		Com	mand	Parameter	End mark
	FFh	30h	30h	01h	5Ch	32h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
Header	Device	e Num	Error	Code		Sta	itus		End mark
FEh	30h	30h	30h	30h	36h	36h	39h	43h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example					e0 e1	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

Parameter Error	•Assigned parameter is an invalid value.

# 8.21 Tilt Maximum Angle Request

# Pan-Tilt Head Control Command Type 1

Function	Return the maxi	Return the maximum value (up end) for tilting angle (position)					
Command	015Ch	015Ch					
Parameter	Length	1 byte					
	Value	3h					
Status	Length	4 byte					
	Value	6500 (9964h)					
Reference	•Status Value(+6500) is the position rotated approx. 130 degrees to upper as						
	zero degree for	horizontal.					

### • Format of Control Code

d0	d1	d2	d3 d4 d5		d6	
Header	Device	e Num	Command		Parameter	End mark
FFh	30h	30h	01h	5Ch	33h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
Header	Device	e Num	Error	Code		Sta	tus		End mark
FEh	30h	30h	30h	30h	39h	39h	36h	34h	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	


Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example					e0 e1	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.22 Pan/Tilt Angle Assignment

Pan-Tilt Head Control Command type 2

Function	Assign the angle (position) for panning/tilting							
Command	0162h							
Parameter	Length	ngth 8 byte						
	Range	Within range of Pan and Tilt Movable Range						
	Default Range	Pan: -90000 to +90000 (5CD8h to A328h)						
		Tilt: -6500 to +6500 (669Ch to 9964h)						
status	None							
Reference	•Parameter Value (1)	LSB) of both Pan/Tilt is equal to approx.0.02 degrees by						
		. (See <b>8.16</b> and <b>8.17</b> )						
		B byte) splits p0~p3 as Pan angle (position) section, and						
	p4~p7 as Tilt (posit	· ·						
	•The right direction of	of Pan Angle (position) is positive and the left one is						
	negative. The upper	direction of Tilt Angle (position) is positive and the						
	lower one is negative							
	<ul> <li>Assigned sample of</li> </ul>	Pan/tilt Angle(position) as below						
	Pan right 90 degr	$rees \Rightarrow +90/0.02 \Rightarrow +4500 \Rightarrow +1194h$						
		$\Rightarrow$ 8000h+1194h = 9194h						
	Tilt lower 30 deg	Tilt lower 30 degrees $\Rightarrow$ -30/0.02 $\Rightarrow$ -1500 $\Rightarrow$ -5DCh						
		$\Rightarrow$ 8000h-5DCh = 7A24h						
	•By issuing this com	By issuing this command, Pan/tilt will be in action simultaneously and <b>Pan</b>						
	and Tilt flag in act	tion among the running status, set 1 and when Pan/Tilt						
	motion stop, Pan/T	<b>'ilt flags</b> in action clear to zero.						



## • Format of Control Command

au	aı	α2	<b>a</b> 3	<b>a</b> 4					
Header	Devic	e Num	Com	mand					
FFh	30h	30h	01h	62h					
	d5	d6	d7	d8	d9	d10	d11	d12	d13
		Pan Angle	Paramete	r	7	Tilt Angle	Parameter		End mark
	<b>n</b> ()	n1	n2	n <sup>2</sup>	n/1	n5	26	n7	EEh

Angle indi	Angle indicates Hexadecimal 8 digits and returns ASCII as parameter value							
Example	Pan <b>i</b> ght	Tilt lov	ver 30 de	egrees				
	Pan				p0	<b>p</b> 1	p2	p3
	+4500	$\Rightarrow$	9194h	$\Rightarrow$	39h	31h	39h	34h
	Tilt				p4	p5	p6	p7
	-1500	$\Rightarrow$	7A24h	$\Rightarrow$	37h	41h	32h	34h

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				TI .	

Error Flag indicates in Hexadecimal 2 digits and returns ASCII code value						
Example					e0 e1	
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h	
■ In case of Busy:	00010000B	$\Rightarrow$	10h	$\Rightarrow$	31h 30h	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

Busy	•In case of executing <b>Shot Memory Movement</b> command
	•In case of Panning by Pan-Tilt Head Control command
	•In case of Tilting by Pan-Tilt Head Control command
	•In case of executing Wiper Control and Washer Control
	commands.
	•In case of executing ND Filter Control command
Parameter Error	•Assigned parameter is an invalid value.

# 8.23 Pan/Tilt Angle Request

# Pan-Tilt Head Control Command type 1

Function	Request tl	Request the angle (position) for panning/tilting					
Command	0163h	0163h					
Parameter	None						
Status	Length	8 byte					
	Range	within range of Pan and Tilt Movable Range					
Reference	•Paramete	er Value (1LSB) of both Pan/Tilt is equal to approx.0.02 degrees by					
	converti	ng to angle ( see <b>8.16</b> and <b>8.17</b> )					
	•Paramete	er section (8 byte) splits s0~s3 as angle (position) section, and s4~s7					
	as Tilt (p	position) section.					
	•This com	nmand returns the angle(position), at the moment of receipt of					
	Commar	nd even through Pan/Tilt is in action except executing Pan-tilt head					
	Initializ	e 1 & 2					

## • Format of Control Command

d0	d1	d2	d3	d4	d5
Header	Device	e Num	Com	End mark	
FFh	30h	30h	01h	63h	EFh

### Answer Format

### ■ In case of no Error

dO	dl	d2	d3	d4					
Header	Devic	e Num	Error Code						
EFh	30h	30h	30h	30h					
	d5	d6	d7	d8	d9	d10	d11	d12	d13
	Pan Angel Status					Tilt Angl	e Status		End mark
	s0	s1	s2	s3	s4	s5	s6	s7	EFh
				$\downarrow$					

The present position indicates in Hexadecimal 8 digits and its ASCII is as parameter value									
Example	Example Pan ight 90 dgrees Tilt lower 30 degrees								
	Pan				p0	p1	p2	p3	
	+4500	$\Rightarrow$	9194h	$\Rightarrow$	39h	31h	39h	34h	
	Tilt				p4	p5	р6	p7	
	-1500	$\Rightarrow$	7A24h	$\Rightarrow$	37h	41h	32h	34h	

# 8.24 Wiper Control

# Pan-Tilt Head Control Command Type 2

Function	Operate the wiper						
Command	017Ah						
Parameter	Length	1byte					
	Value	0h					
Status	None						
Reference	•The wiper pe	erforms one reciprocating operation each time this command is					
	issued.	issued.					
	•A command	error is returned if the outdoor option is not installed.					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Command		Parameter	
FFh	30h	30h	01h	7Ah	30h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	h e0 e		EFh
			•	11	•

 $\downarrow \downarrow$ 

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value								
Example				e0	e1			
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h			
■ In case of Busy:	$00010000B \Rightarrow$	10h	$\Rightarrow$	31h	30h			
■ In case of Command Erro	or: $00110000B \Rightarrow$	30h	$\Rightarrow$	33h	30h			
■ In case of Parameter Erro	or: $01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h			

	<u> </u>						
Command Error	•The outdoor option is not installed.						
Busy	•In case of executing <b>Shot Memory</b> command.						
	•In case of Panning by Pan-tilt head Control command						
	•In case of Tilting by Pan-tilt head Control command						
	•In case of executing Wiper Control and Washer Control						
	commands.						
	•In case of executing <b>ND Filter Control</b> command.						
Parameter Error	•Assigned parameter is an invalid value.						

## 8.25 Washer Control

# Pan-Tilt Head Control Command Type 2

Function	Operate the washer					
Command	017Ah					
Parameter	Length	1byte				
	Value	1h				
Status	None					
Reference	•Executing this	command once performs four wiper cycles, and the washer				
	terminal is set	terminal is set to ON during the first two cycles.				
	•A command er	ror is returned if the outdoor option is not installed.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Command		Parameter	
FFh	30h	30h	01h	7Ah	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh

 $\downarrow \downarrow$ 

Error Flag indicates in 2 dig	its Hexadecimal and r	eturns AS	SCII cod	le value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Busy:	$00010000B \Rightarrow$	10h	$\Rightarrow$	31h	30h
■ In case of Command Err	or: $00110000B \Rightarrow$	30h	$\Rightarrow$	33h	30h
■ In case of Parameter Erro	or: $01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h

	5
Command Error	•The outdoor option is not installed.
Busy	•In case of executing <b>Shot Memory</b> command.
	•In case of Panning by Pan-tilt head Control command
	•In case of Tilting by Pan-tilt head Control command
	•In case of executing Wiper Control and Washer Control
	commands.
	•In case of executing <b>ND Filter Control</b> command.
Parameter Error	•Assigned parameter is an invalid value.

# 8.26 Tally OFF

# Pan-Tilt Head Control Command Type 2

Function	Turn off the ta	Turn off the tally		
Command	017Bh	17Bh		
Parameter	Length	1byte		
	Value	0h		
Status	None			
Reference				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	7Bh	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digit	ts Hexadecimal and r	eturns AS	CII cod	le value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

# **8.27** Tally ON

# Pan-Tilt Head Control Command Type 2

Function	Turn on the tal	Turn on the tally		
Command	017Bh	17Bh		
Parameter	Length	1byte		
	Value	1h		
Status	None			
Reference				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	7Bh	31h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digit	s Hexadecimal and r	eturns AS	CII cod	le value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.

## 8.28 AUX OUT OFF

# Pan-Tilt Head Control Command Type 2

Function	Set the AUX or	Set the AUX output terminal (non-contact output) to off		
Command	0171h	0171h		
Parameter Length		2byte		
	Value	1 <sup>st</sup> byte : 0h 2 <sup>nd</sup> byte: 0h		
		2 <sup>nd</sup> byte: 0h		
Status	None			
Reference	•The AUX status is saved even after the pan-tilt head is reset.			

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	71h	30h	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				П	

Error Flag indicates in 2 digits	Hexadecima	and retu	rns ASC	II code v	alue	
Example					e0	e1
■ In case of No Error:	0000000B	$\Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## **8.29 AUX OUT ON**

Pan-Tilt Head Control Command Type 2

Function	Set the AUX ou	Set the AUX output terminal (non-contact output) to on			
Command	0171h	0171h			
Parameter	Length 2byte				
	Value	1 <sup>st</sup> byte : 0h 2 <sup>nd</sup> byte: 1h			
		2 <sup>nd</sup> byte: 1h			
Status	None				
Reference	•The AUX status is saved even after the pan-tilt head is reset.				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	71h	30h	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				Ш	

Error Flag indicates in 2 digi	ts Hexadecimal and r	eturns AS	SCII cod	e value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	or: $01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

## 8.30 AUX Status Request

Pan-Tilt Head Control Command Type 1

Function	Return the prese	Return the present AUX status information			
Command	01EAh	1EAh			
Parameter Length		1byte			
	Value	Oh			
Status	Length	2byte			
	Value	See below			
Reference	•See the status details below.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	EAh	30h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	
Header	Device	Num	Error Code		AUX Status		End mark	
FEh	30h	30h	30h	30h	s0	s1	EFh	
<u> </u>								

AUX Status indicates in Hexadecimal 1 digit and parameter value is its ASCII code						
Example:			s0	s1		
	11	$\Rightarrow$	31h	31h		

### ■ In case of Error

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h	30h	e0	e1	EFh	
				П		

Error Flag indicates in 2 digits Hexadecimal and re	turns AS	CII code	e value	
Example			e0	e1
■ In case of Parameter Error: 01010000B ⇒	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.

## • Status Bit Assignment

By assigning the AUX status to bits as shown below, it can be expressed in two digits of hexadecimal. The ASCII code is returned.

Bit	Description					
b7	Reserve					
b6	Reserve					
b5	Reserve					
b4	AUX IN status ON: 1/OFF: 0					
b3	Reserve					
b2	Reserve					
b1	Reserve					
b0	AUX OUT status ON: 1/OFF: 0					

Example: For AUX OUT ON, AUX IN ON: 11h  $\Rightarrow$  31h 31h

## 8.31 Housing Fan Status Request

Pan-Tilt Head Control Command Type 1

Function	Return the prese	Return the present housing fan status information				
Command	01EAh	01EAh				
Parameter	Length	1byte				
	Value	Ah				
Status	Length	2byte				
	Value	See below				
Reference	•See the status details below.					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	EAh	41h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	
Header	Device	Num	Error Code		Fan Status		End mark	
FEh	30h	30h	30h	30h	s0	s1	EFh	
<b>\</b>								

Fan Status indicates in Hexadecimal 1 digit and parameter value is its ASCII code						
Example:			s0	s1		
	11	$\Rightarrow$	31h	31h		

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and re	turns AS	CII code	e value	
Example			e0	e1
■ In case of Parameter Error: 01010000B ⇒	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
I didifficted Lifter	Assigned parameter is an invalid value.

## • Status Bit Assignment

By assigning the Fan status to bits as shown below, it can be expressed in two digits of hexadecimal. The ASCII code is returned.

Bit	Description			
b7	Reserve			
b6	Reserve			
b5	Reserve			
b4	Fan status ON: 1/OFF: 0			
b3	Reserve			
b2	Reserve			
b1	Reserve			
b0	Fan alarm ON: 1/OFF: 0			

Example: For Fan ON, Alarm ON: 11h⇒ 31h 31h

# 8.32 Washer Output OFF

Pan-Tilt Head Control Command Type 1

Function	Turn off the w	Turn off the washer terminal output		
Command	0171h			
Parameter	Length	2byte		
	Value	1 <sup>st</sup> byte : Bh 2 <sup>nd</sup> byte: 0h		
		2 <sup>nd</sup> byte: 0h		
Status	None			
Reference				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Com	mand	Paran	neter	End mark
FFh	30h	30h	01h	71h	42h	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				TI .	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example				e0	e1	
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h	
■ In case of Parameter Erro	or: $01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h	

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

# 8.33 Washer Output ON

# Pan-Tilt Head Control Command Type 1

Function	Turn on the washer terminal output			
Command	0171h			
Parameter	Length	2byte		
	Value	1 <sup>st</sup> byte : Bh		
		2 <sup>nd</sup> byte: 1h		
Status	None			
Reference	•The wiper will not work with this command. It is used for removing air from			
	tubes during washer unit installation.			
	•The Washer Output command automatically changes to Off status			
	approximately one minute after turning On the command.			
	•As well as the Washer Output OFF command, the Washer Output command			
	can turns the W	Vasher Output off after the wiper works for two cycles.		

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Com	mand	Paran	neter	End mark
FFh	30h	30h	01h	71h	42h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value					
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	or: $01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
-----------------	------------------------------------------

### 9. Details of Camera Control Command

## 9.1 Camera Version Request

## Pan-Tilt Head Control Command Type 1

Function	Return the came	Return the camera version value			
Command	01BEh				
Parameter	Length	Length 1byte			
	Value 0h				
Status Length 2byte					
	Value 01h				
Reference	•Returns the camera version value in 2 digits Hexadecimal.				
	•In the future, the status (version number) could change.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	BEh	30h	EFh

### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	Num	Error	Code	Version	n Value	End mark
FEh	30h	30h	30h	30h	s0	s1	EFh

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
			•	11	•

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value				
Example			e0	e1
■ In case of Parameter Error: 01010000B	$\Rightarrow$ 50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.	
-----------------	------------------------------------------	--

## 9.2 Camera OFF

# Camera Control Command Type 2

Function	Turn off the power to the camera section				
Command	01A0h	01A0h			
Parameter	Length	Length 1 byte			
	Value	0h			
Status	None	None			
Reference	•To power Camera section OFF(Picture signal of camera comes out OFF)				
	•By issuing this	•By issuing this command, flag of <b>Camera Power OFF</b> command is set as 1.			

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A0h	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				JI.	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value					
Example					e0 e1
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h

Parameter Error	•Assigned parameter is an invalid value

## 9.3 Camera ON

# Camera Control Command Type 2

Function	Turn on the power to the camera section				
Command	01A0h				
Parameter	Length	1 byte			
	Value	1h			
Status	None				
Reference	•To power Cam	era section Power ON (Picture signal of camera turns out)			
	•Camera section	set values come out default value.			
	•By issuing this	command, the camera power off flag is cleared to 0, while in			
	the operating st	tatus.			
	•The camera bu	sy flag of extended operation status is set to "1" while			
	executing this	command. The camera busy flag will be cleared after the			
	camera ON pro	ocess completes (the process takes approximately 15 seconds			
	to complete).				
	•Check the camera busy flag, to check that the camera power is on using				
command, and that the camera control and camera settings are possil					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A0h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

	<u>*</u>					
Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example					e0 e1	
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	

	8
Parameter Error	•Assigned parameter is an invalid value.

### 9.4 Focus Auto

### Camera Control Command Type 2

Function	Set the auto focus (AF) mode				
Command	01A1h				
Parameter	Length	Length 1 byte			
	Value	Value 0h			
Status	None	None			
Reference	•Flags in <b>Focu</b>	sing of Operation Status and Manual Focus cleared to zero			
	at AF Mode.	at AF Mode.			
	•AF Mode sets default value at the time of executing <b>Camera Reset</b> and				
	Camera ON commands during power ON.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A1h	30h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h 30h 30h  $\Rightarrow$ ■ In case of Parameter Error : 01010000B 50h 35h 30h  $\Rightarrow$ ■ In case of Mode Error: 10010000B 90h 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>
	•In case of executing One-shot AF

### 9.5 Focus Manual

### Camera Control Command Type 2

Function	Stop the focusing operation and set the manual focus (MF) mode				
Command	01A1h				
Parameter	Length 1 byte				
	Value	Value 1h			
Status	None	None			
Reference	•In case of AF a	and INF (infinity) Mode, cancels AF Mode and set MF Mode.			
	•To stop focus of	•To stop focus operation under focusing by MF mode.			
	Flags in <b>Focusing</b> of Operation Status comes out zero and <b>Manual Focus</b>				
	come out 1.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A1h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 00h 30h 30h 0000000B  $\Rightarrow$ ■ In case of Parameter Error : 01010000B 50h 35h 30h  $\Rightarrow$ ■ In case of Mode Error: 10010000B 90h 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>
	•In case of executing One-shot AF

## 9.6 Focus Fixed at Infinity

## Camera Control Command Type 2

Function	Fix the focus to infinity (INF) mode					
Command	01A1h	01A1h				
Parameter	Length 1 byte					
	Value Bh					
Status	None					
Reference	•In INF mode, the <b>focusing flag</b> in operating status, and the <b>manual focus</b>					
	flag are set to 0.					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	A1h	42h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of No Error: 0000000B  $00h \Rightarrow$ 30h 30h ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error : 10010000B 90h 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>
	•In case of executing One-shot AF

### 9.7 Focus Near

# Camera Control Command Type 2

Function	Move the focus point near				
Command	01A1h				
Parameter	Length	1 byte			
	Value	2h			
Status	None				
Reference	•If operating in the NEAR direction with this command, the <b>focusing flag</b> in				
	operating statu	s is set to 1.			
	•If operating in the NEAR direction with this command, it is possible to stop				
	movement using the <b>focus MANUAL</b> command.				
	•If operating in the NEAR direction with this command, it is possible to				
	forcibly stop movement using the <b>focus FAR</b> command.				
	•The focusing movement stops at Focus Operation Limit (Near end), and the				
	<b>focusing flag</b> in operating status is set to 0.				

## • Format of Control Code

	d0	d1	d2	d3	d4	d5	d6
Н	eader	Device	e Num	Command		Parameter	End mark
I	Fh	30h	30h	01h	A1h	32h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example	e0 e1					
■ In case of No Error:	$00000000B \Rightarrow 00h \Rightarrow 30h 30h$					
■ In case of Parameter Error:	$01010000B \Rightarrow 50h \Rightarrow 35h 30h$					
■ In case of Mode Error:	$10010000B \Rightarrow 90h \Rightarrow 39h 30h$					

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is <b>ON</b>
	•Not in status of Manual Focus
	•In case of executing One-shot AF

### 9.8 Focus Far

### Camera Control Command Type 2

Function	Move the focus point far			
Command	01A1h			
Parameter	Length	1 byte		
	Value	3h		
Status	None			
Reference	<ul> <li>•If operating in the FAR direction with this command, the focusing flag in operating status is set to 1.</li> <li>•If operating in the FAR direction with this command, it is possible to stop movement using the focus MANUAL command.</li> <li>•If operating in the FAR direction with this command, it is possible to forcibly stop movement using the focus NEAR command.</li> <li>•The focusing movement stops at Focus Operation Limit (Far end), and the</li> </ul>			
	<b>focusing flag</b> in operating status is set to 0.			

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Devic	e Num	Command		Parameter	End mark
FFh	30h	30h	01h	A1h	33h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example e0 e1

■ In case of No Error: 00000000B ⇒ 00h ⇒ 30h 30h

■ In case of Parameter Error: 01010000B ⇒ 50h ⇒ 35h 30h

■ In case of Mode Error: 10010000B ⇒ 90h ⇒ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is <b>ON</b>
	•Not in status of Manual Focus
	•In case of executing One-shot AF

## 9.9 One-shot AF

Camera Control Command Type 2

Function	Perform the o	Perform the one-shot AF				
Command	01A1h	01A1h				
Parameter	Length	Length 1 byte				
	Value	Ah				
Status	None	None				
Reference	•One-shot AF	•One-shot AF operation takes approximately seven seconds.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A1h	41h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				III	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example e0 e1							
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>
	•When Focus is fixed at infinity
	•In case of executing One-shot AF
	•In case of executing <b>Shot Memory</b> command.

## 9.10 Zoom Stop

Camera Control Command Type 2

Function	Stop the zooming operation					
Command	01A2h					
Parameter	Length	1 byte				
	Value	0h				
Status	None					
Reference	•Flags in <b>Zoo</b>	•Flags in <b>Zooming</b> of Operation Status are cleared to zero.				
	•To set Zoom Stop by default at the moment of setting <b>Camera Reset</b> and					
	Camera ON	commands during power ON.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A2h	30h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				- III	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h 30h 30h ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error : 10010000B 90h 39h 30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

## 9.11 Zoom Wide

# Camera Control Command Type 2

Function	Zoom to wide side						
Command	01A2h						
Parameter	Length	Length 1 byte					
	Value 1h						
Status	None						
Reference	•If operating in	•If operating in the Wide direction with this command, the <b>Zooming flag</b> in					
	operating stat	operating status is set to 1.					
	•Movement sp	eed can be set using <b>Zoom Speed Assignment</b> command.					
	•Movement ca	•Movement can be stopped using the <b>Zoom Stop</b> command.					
	•If operating in the Wide direction with this command, it is possible to						
	forcibly stop movement using the <b>Zoom Tele</b> or <b>Zoom Hi Tele</b> command.						
	•The zooming movement stops at Zooming Wide Operation Limit (optical						
	widest end), a	and the <b>zooming flag</b> is cleared to zero.					

## • Format of Control Code

d0		d1	d2	d3	d4	d5	d6
Head	ler	Device Num		Command		Parameter	End mark
FFI	1	30h	30h	01h	A2h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				TI .	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example					e0 e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is <b>ON</b>

## 9.12 Zoom Tele

# Camera Control Command Type 2

Function	Zoom to telephoto side						
Command	01A2h	01A2h					
Parameter	Length 1 byte						
	Value	2h					
Status	None						
Reference	•If operating in	the Tele direction with this command, the <b>Zooming flag</b> in					
	operating statu	s is set to 1.					
	•Movement spe	ed can be set using <b>Zoom Speed Assignment</b> command.					
	•Movement can	be stopped using the <b>Zoom Stop</b> command.					
	•If operating in	the Tele direction with this command, it is possible to forcibly					
	stop movemen	t using the <b>Zoom Wide</b> or <b>Zoom Hi Wide</b> command.					
	•The zooming movement stops at Zooming Telephoto Operation Limit						
	(Optical interlo	(Optical interlocking mode: Maximum digital magnification, Independent					
	mode: optical t	elephoto end), and the <b>zooming flag</b> is cleared to zero.					

## • Format of Control Code

d0	d1 d2		d3	d4	d5	d6	
Header	Device Num		Command		Parameter	End mark	
FFh	30h	30h	01h	A2h	32h	EFh	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value								
Example					e0 e1			
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h			
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h			
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h			

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

## 9.13 Zoom Hi Wide

# Camera Control Command Type 2

Function	Zoom to wide side in high speed						
Command	01A2h	01A2h					
Parameter	Length	1 byte					
	Value	3h					
Status	None						
Reference	•If operating	in the Wide direction with this command, the <b>Zooming flag</b> in					
	operating sta	ntus is set to 1.					
	•Movement s	peed can be set using <b>Zoom Speed Assignment</b> command.					
	•Movement of	can be stopped using the <b>Zoom Stop</b> command.					
	•If operating	in the Wide direction with this command, it is possible to					
	forcibly stop movement using the <b>Zoom Tele</b> or <b>Zoom Hi Tele</b> command.						
	•The zooming movement stops at Zooming Wide Operation Limit (optical						
	widest end),	and the <b>zooming flag</b> is cleared to zero.					

## • Format of Control Code

d0	d1 d2		d3	d4	d5	d6	
Header	Devic	Device Num		Command		End mark	
FFh	30h	30h 30h		A2h	33h	EFh	

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example					e0 e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

### 9.14 Zoom Hi Tele

### Camera Control Command Type 2

Function	Zoom to telephoto side in high speed					
Command	01A2h					
Parameter	Length	Length 1 byte				
	Value	4h				
Status	None					
Reference	•If operating in	the Tele direction with this command, the <b>Zooming flag</b> in				
	operating statu	s is set to 1.				
	•Movement spe	ed can be set using <b>Zoom Speed Assignment</b> command.				
	•Movement can	be stopped using the <b>Zoom Stop</b> command.				
	•If operating in	the Tele direction with this command, it is possible to forcibly				
	stop movement using the <b>Zoom Wide</b> or <b>Zoom Hi Wide</b> command.					
	•The zooming movement stops at Zooming Telephoto Operation Limit					
	(Optical interlo	(Optical interlocking mode: Maximum digital magnification, Independent				
	mode: optical t	elephoto end), and the <b>zooming flag</b> is cleared to zero.				

### • Format of Control Code

_	d0	d1	d2	d3	d4	d5	d6
Ī	Header	Device Num		Command		Parameter	End mark
	FFh	30h	30h	01h	A2h	34h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h 30h 30h  $\Rightarrow$ ■ In case of Parameter Error : 50h 01010000B  $\Rightarrow$ 35h 30h ■ In case of Mode Error : 90h 10010000B 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

# 9.15 Zoom Position Assignment

Camera Control Command Type 2

Function	Move to the assigned zooming position					
Command	01A3h					
Parameter	Length 2 byte					
	Range Optical interlocking mode: 00h (Wide) to EEh					
	_	Independent mode: 00h (Wide) to 80h (Telephoto)				
Status	None					
Reference	•When the setting of the digital zoom operation is the optical interlocking					
	mode, 00 (00h)	to 128 (80h) is the optical region; 129 (81h) to 238 (EEh) is				
	the digital zoor	n region.				
	•When the setting	ng is the Independent mode, the optical zoom position between				
	00 (00h) and 12	28 (80h) can be assigned. The digital zoom position does not				
	change.					
		ing of Operation Status are set to 1. Zooming will				
	-	ing assigned position and <b>flag in zooming</b> is cleared to 0.				
	•To stop zoomir	ng by <b>Zoom Stop</b> Command and <b>flag in zooming</b> is cleared to				
	zero.					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Com	mand	Paran	neter	End mark
FFh	30h	30h	01h	A3h	p0	p1	EFh
				П			

Zoom position indicate	es in Hexa	adecimal	2 digits a	nd parar	neter valu	e is its ASCII code	
Example					p0	p1	
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
•Example					e0 e1	
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h	

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

## 9.16 Zoom Position Request

Camera Control Command Type 1

Function	Return the present zooming position					
Command	01A4h	01A4h				
Parameter	None					
Status	Length 2 byte					
	Range	Optical interlocking mode: 00h (Wide) to EEh (Telephoto)				
		Independent mode: 00h (Wide) to 80h (Telephoto)				
Reference	•To assign zo	om position by Pre-Assigned Step Value, within movable range.				
	• When the se	etting of the digital zoom operation is the optical interlocking				
	mode, 00 (00	Oh) to 128 (80h) is the optical region; 129 (81h) to 238 (EEh) is				
	the digital zo	the digital zoom region.				
	• When the setting is the Independent mode, the optical zoom position					
	between 00 (	between 00 (00h) and 128 (80h) is returned. It does not depend on the digital				
	zoom magni	zoom magnification.				

### • Format of Control Command

d0	d1	d2	d3	d4	d5
Header	Device Num		Com	End mark	
FFh	30h	30h	01h	A4h	EFh

## • Answer format

### ■ In case of No error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Error Code		Zoom Position		End mark
FEh	30h	30h	30h	30h	s0	s1	EFh
				- 11			

Present position indicates in Hexadecimal 2 digits and its ASCII code is Status							
	value.						
Example:						s0	s1
		64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates Hexadecimal 2 digits and returns ASCII value					
Example	e0 e1				
■ In case of Mode Error:	$10010000B \Rightarrow 90h \Rightarrow 39h 30h$				

	8
Mode Error	•Not in status of Camera ON

### 9.17 Zoom Speed Assignment

Camera Control Command Type 1

Function	Assign the zoon	Assign the zooming speed			
Command	01B4h	)1B4h			
Parameter	Length 2 byte				
	Range	1 <sup>st</sup> byte: 1			
	_	$2^{\text{nd}}$ byte: 0~7 (0h~7h)			
Status	None	None			
Reference	•Speed set by th	•Speed set by this command is reflected in <b>Zoom Wide</b> and <b>Zoom Tele</b>			
	commands.				
	•Default value i	s 7.			

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	B4h	31h	p1	EFh
$\overline{\hspace{1cm}}$							

Zoom speed indicates in Hexadecimal 1 digit and parameter value is its ASCII code

Example: p1  $4 \Rightarrow 4h \Rightarrow 34h$ 

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value •Example e0 e1 ■ In case of No Error: 00000000B 00h 30h 30h ■ In case of Parameter Error : 01010000B 50h 35h 30h ■ In case of Mode Error: 10010000B 90h  $\Rightarrow$ 39h 30h

	0
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.18 Zoom Speed Request

Camera Control Command Type 1

Function	Return the prese	Return the present zooming speed				
Command	01B4h	01B4h				
Parameter Length 1 byte		1 byte				
	Value	2h				
Status	Length	1 byte				
	Range	0~7 (0h~7h)				
Reference	•Default value is 7					

### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	B4h	32h	EFh

### Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Error	Code	Speed	End mark
FEh	30h	30h	30h	30h	s0	EFh
				$\downarrow$		

Zoom speed indicates in Hexadecimal 1 digit and status value is its ASCII code						
Example:					p0	
	4	$\Rightarrow$	4h	$\Rightarrow$	34h	

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
•				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value					
•Example					e0 e1
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h

	C
Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.19 Digital Zoom Magnification Assignment (XU-81)

Camera Control Command Type 2

Function	Set the digital zoom magnification				
Command	01DAh				
Parameter	Length	2 byte			
	Range	0 to 110 (00h to 6Eh)			
Status	None				
Reference	•The setting can	be made between 1.0x to 12.0x at 0.1x intervals.			
	•It is valid when	the setting of digital zoom operation is the Independent mode.			
	When the setting returned.	ng is the Optical interlocking mode, the command error is			
	•When the power command is 0	er is on, the initial value for camera reset and camera ON			
	•It is valid for XU-81 only.				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Com	mand	Paran	neter	End mark
FFh	30h	30h	01h	DAh	p0	p1	EFh
				JI.	,		

Digital zoom magnificat ASCII code	tion indic	cates in F	Hexadecin	nal 2 dig	gits and par	ameter value is its
Example:	110	$\Rightarrow$	6Eh	$\Rightarrow$	p0 36h	p1 45h

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				.II.	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

Command Error	•The digital zoom mode setting is the Optical interlocking mode.
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

# ● Digital Zoom Magnification Table (Prototypical value)

Parameter	Digital Zoom Magnification
00h	1.0x
0Ah	2.0x
14h	3.0x
1Eh	4.0x
28h	5.0x
32h	6.0x
3Ch	7.0x
46h	8.0x
50h	9.0x
5Ah	10.0x
64h	11.0x
6Eh	12.0x

**Note:** The setting can be made within the above parameter range at 0.1x intervals.

# 9.20 Digital Zoom Magnification Status Request (XU-81)

Camera Control Command Type 1

Function	Return the digita	Return the digital zoom magnification status information					
Command	01C6h						
Parameter	Length	1 byte					
	Value	10 (Ah)					
Status	Length	2 byte					
	Value	0 to 110 (00h to 6Eh)					
Reference	•For the detailed	relation between the parameter values and the digital zoom					
	magnification,	refer to Digital Zoom Magnification Table in "Digital Zoom					
	Magnification A	Magnification Assignment."					
	•It is valid for X	U-81 only.					

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	C6h	41h	EFh

### Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	Num	Error	Code	Shutte	r Status	End mark
FEh	30h	30h	30h	30h	s0	s1	EFh
<b>\</b>							

Digital zoom magnification status indicates in Hexadecimal 2 digits and status value is its ASCII code

Example:  $\begin{array}{ccc} & & & & & & & & & \\ & & & & & & & \\ & & & & & & \\ & & & & & & \\ & & & & & & \\ & & & & & & \\ & & & & & & \\ & & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & \\ & & & \\ & & \\ & & & \\ & & \\ & & \\ & & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\$ 

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
•Example					e0 e1		
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.21 Color Bar OFF

# Camera Control Command Type 2

Function	Turn off the color bar output and switch the output video to camera video						
Command	01B8h	01B8h					
Parameter	Length 1 byte						
	Value	0h					
Status	None	None					
Reference	•When the power is on, the default settings are made when the <b>Camera Reset</b>						
	and Camera ON commands are executed.						

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		um Command		Parameter	End mark
FFh	30h	30h	01h	B8h	30h	EFh

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.	
Mode Error	•Not in status of <b>Camera ON</b>	

### 9.22 Color Bar ON

Camera Control Command Type 2

Function	Switch the ou	Switch the output video to color bars					
Command	01B8h	01B8h					
Parameter	Length	Length 1 byte					
	Value	1h					
Status	None						
Reference							

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	B8h	31h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of No Error:  $00000000B \Rightarrow$ 00h 30h 30h  $\Rightarrow$ ■ In case of Parameter Error:  $01010000B \Rightarrow$ 50h 35h 30h ■ In case of Mode Error:  $10010000B \Rightarrow$ 30h 90h 39h  $\Rightarrow$ 

Parameter Error	•Assigned parameter is an invalid value.		
Mode Error	•Not in status of <b>Camera ON</b>		

### 9.23 Color Bar Status Request

Camera Control Command Type 1

Function	Return the present color bar status						
Command	01C5h						
Parameter	Length	Length 1 byte					
	Value 2h						
Status	Length 1 byte						
	Range 0, 1 (0h, 1h)						
Reference	•For the detailed relation between the status and the color bar status, refer to						
	Color Bar Status Value Table below.						

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C5h	32h	EFh

### Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Error Code		Status	End mark
FEh	30h	30h	30h	30h	s0	EFh
				TI .		

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

•Example e0 e1

■ In case of Parameter Error : 01010000B ⇒ 50h ⇒ 35h 30h

■ In case of Mode Error : 10010000B ⇒ 90h ⇒ 39h 30h

### • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

### • Color Bar Status Value Table

S0	Color Bar Status
30h	OFF (video output)
31h	ON

## 9.24 Shooting Mode Switching

Camera Control Command Type 2

Function	Switch the camera shooting mode				
Command	0184h				
Parameter	Length 1 byte				
	Range 0 to 4 (0h to 4h)				
Status	None	None			
Reference	•The available f	functions are limited depending on the shooting mode. (See the			
	Shooting Mode	Shooting Mode Table.)			
	•To set to <b>Auto</b>	•To set to <b>Auto</b> in default value at the moment of <b>Camera Reset</b> and <b>Camera</b>			
	ON commands	in status of Power ON.			

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	84h	p0	EFh
				П		

The camera shooting mode parameter value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter.

Example: p0 p0 p0 p0 p0 p0

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e1 e0■ In case of No Error: 00h  $00000000B \Rightarrow$ 30h 30h ■ In case of Parameter Error:  $01010000B \Rightarrow$ 50h 35h 30h  $\Rightarrow$ ■ In case of Mode Error:  $10010000B \Rightarrow$ 90h 39h 30h  $\Rightarrow$ 

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is <b>ON</b>

# • Shooting Mode Table

Parameter Value	0h	1h	2h	3h	4h
Shooting Mode	Auto	Manual	Night	Shutter Priority	Iris Priority
Gain	Auto	0	Auto	Auto	Auto
Shutter	Auto (No accumulation)	0	Auto (Accumulation)	0	Auto (No accumulation)
Iris	Auto	0	Auto	Auto	0
AutoICR ON/OFF	× (Fixed at OFF)	X (Fixed at OFF)	0	X (Fixed at OFF)	× (Fixed at OFF)
IR Filter	0	0	0	0	0
AE compensation	0	×	0	0	0
Color Bar	0	0	0	0	0
WDR	0	0	0	0	0
ND Filter	0	0	0	0	0
White Balance	0	0	0	0	0
Edge compensation	0	0	0	0	0
Black Level	0	0	0	0	0

O: Operation is enabled

X: Operation is disabled

Auto: Automatically adjusted

### 9.25 Shooting Mode Status Request

Camera Control Command Type 1

Function	Return the came	Return the camera shooting mode status information			
Command	01C5h				
Parameter	Length	1 byte			
	Value 3h				
Status	Length 1 byte				
	Range 0 to 4 (0 to 4h)				
Reference	•For the detailed relation between the status and the shooting mode status,				
	refer to Shootin	g Mode Status Value Table below.			

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C5h	33h	EFh

#### Answer Format

### ■In case of No error

	d0	d1	d2	d3	d4	d5	d6
	Header	Device Num		Error Code		Status	End mark
	FEh	30h	30h	30h	30h	s0	EFh
-					- III		

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
			•	11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

•Example e0 e1

■ In case of Parameter Error : 01010000B ⇒ 50h ⇒ 35h 30h

■ In case of Mode Error : 10010000B ⇒ 90h ⇒ 39h 30h

## • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

### Shooting Mode Status Value Table

S0	Shooting Mode Status
30h	Auto
31h	Manual
32h	Night
33h	Priority to Shutter
34h	Priority to Iris

# **9.26** Shutter Speed 1/60

## Camera Control Command Type 2

Function	Set the shutter speed to 1/60 sec. (when the video rate setting is 59.94)				
Command	01A8h				
Parameter	Length 1 byte				
	Value 1h				
Status	None				
Reference	•To be able to change when the shooting mode is <b>Manual and Shutter</b>				
	Priority.				
	•The Shutter Speed is set to 1/50 sec. when the frame rate is set to 50.				

### • Format of Control Command

d0	d1	d2	d3 d4 d5		d6	
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A8h	31h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value •Example e0 e1 ■ In case of No Error: 0000000B 00h 30h 30h  $\Rightarrow$ ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error: 10010000B 90h ⇒ 39h 30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is <b>Auto</b> , <b>Night</b> , <b>or Iris Priority mode</b> .
	•In status Color bar output is <b>ON</b>

# **9.27** Shutter Speed 1/100

# Camera Control Command Type 2

Function	Set the shutter speed to 1/100 sec.				
Command	01A8h				
Parameter	Length	Length 1 byte			
	Value 2h				
Status	None				
Reference	•To be able to change when the shooting mode is <b>Manual and Shutter</b>				
	Priority.				

## • Format of Control Command

(	d0	d1	d2 d3 d4 d5		d6		
He	ader	Device Num		Command		Parameter	End mark
F	Fh	30h	30h	01h	A8h	32h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0 e1		EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
•Example					e0 e1	
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h	
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h	
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h	

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON.</b>
	•The shooting mode is <b>Auto</b> , <b>Night</b> , <b>or Iris Priority mode</b> .
	•In status Color bar output is <b>ON</b>

# 9.28 Shutter Speed Assignment

Camera Control Command Type 2

Function	Assign the shutter speed.				
Command	01ADh	01ADh			
Parameter	Length 1 byte				
	Range	0~4 (0h~4h)			
Status	None	None			
Reference	•See the follo	wing table for relation between Parameter value and the shutter			
	speed. Howe	speed. However, they vary depending on the frame rate setting.			
	•To be able to change when the shooting mode is <b>Manual and Shutter</b>				
	Priority.				

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h	30h	01h	ADh	p0	EFh
				Ш		

Shutter Speed Parame its ASCII code.	ter indica	tes in Hex	kadecima	l 1 digit a	and paramete	er value is
Example:	3	$\Rightarrow$	3h	$\Rightarrow$	p0 33h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digit	s Hexadecimal and 1	eturns AS	SCII cod	e value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is <b>Auto</b> , <b>Night</b> , <b>or Iris Priority mode</b> .
	•In status Color bar output is <b>ON</b>

# • Shutter Speed Corresponding Table

Parameter	Shutter Speed				
Farameter	59.94	50			
00	2/1	2/1			
01	1/15	1/12			
02	1/60	1/50			
03	1/100	1/100			
04	1/1000	1/1000			

## 9.29 Shutter Speed Status Request

## Camera Control Command Type 1

Function	Return the prese	Return the present shutter speed status information			
Command	01C5h				
Parameter	Length 1 byte				
	Value	5h			
Status	Length	1 byte			
	Range	0 to 4 (0 to 4h)			
Reference	For the detailed relation between the status and the shutter speed status, refer				
	to Shutter Speed	to Shutter Speed Status Value Table below.			

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C5h	35h	EFh

### Answer Format

In case of No error

	d0	d1	d2	d3	d4	d5	d6
	Header	Device Num		Error Code		Status	End mark
	FEh	30h	30h	30h	30h	s0	EFh
-					- III		

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

•Example e0 e1

■ In case of Parameter Error : 01010000B ⇒ 50h ⇒ 35h 30h

■ In case of Mode Error : 10010000B ⇒ 90h ⇒ 39h 30h

### • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

### Shooting Mode Status Value Table

S0	Shutter Speed Status
30h	2s (2 to 1/8s)
31h	1/15s (1/15 to 1/30s)
32h	1/60s
33h	1/100s (1/90 to 1/100s)
34h	1/1000s (1/125 to 1/10000s)

# 9.30 Shutter Speed Detailed Setting

Camera Control Command Type 2

Function	Set the shutter s	Set the shutter speed				
Command	019Dh					
Parameter	Length	2 byte				
	Range	121 to 143 (79h to 8Fh)				
Status	None					
Reference	•See the follow	ing table for relation between Parameter value and the shutter				
	speed. However, they vary depending on the frame rate setting.					
	•To be able to change when the shooting mode is <b>Manual and Shutter</b>					
	Priority.					

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Com	mand	Parai	neter	End mark
FFh	30h	30h	01h	9Dh	p0	p1	EFh
				Ш			

Shutter Speed Para is its A	ameter indicate SCII code.	s in He	xadecimal	2 digits	and para	meter value
Example:					p0	p1
	128	$\Rightarrow$	80h	$\Rightarrow$	38h	30h

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				.II.	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is <b>Auto</b> , <b>Night</b> , <b>or Iris Priority mode</b> .
	•In status Color bar output is <b>ON</b>

# • Shutter Speed Corresponding Table

Speed Corresponding Table							
Shutter	Speed						
59.94	50						
2	2						
1	1						
1/2	1/1.5						
1/4	1/3						
1/8	1/6						
1/15	1/12						
1/30	1/25						
1/60	1/50						
1/90	1/90						
1/100	1/100						
1/125	1/125						
1/180	1/180						
1/250	1/250						
1/350	1/350						
1/500	1/500						
1/725	1/725						
1/1000	1/1000						
1/1500	1/1500						
1/2000	1/2000						
1/3000	1/3000						
1/4000	1/4000						
1/6000	1/6000						
1/10000	1/10000						
	Shutter 59.94 2 1 1/2 1/4 1/8 1/15 1/30 1/60 1/90 1/100 1/125 1/180 1/250 1/350 1/500 1/725 1/1000 1/1500 1/2000 1/3000 1/4000 1/6000						

## 9.31 Shutter Speed Detailed Status Request

Camera Control Command Type 1

Function	Return the shutter speed detailed status information						
Command	01C6h	01C6h					
Parameter	Length	1 byte					
	Value	1h					
Status	Length	2 byte					
	Range	121 to 143 (79h to 8Fh)					
Reference	•See the following table for relation between Parameter value and the shutter						
	speed.						

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	C6h	31h	EFh

### Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	e Num	Error	Code	Shutter	status	End mark
FEh	30h	30h	30h	30h	s0	s1	EFh
				- 11			

Shutter Speed Status indicates in Hexadecimal 2 digits and parameter value is its ASCII code.

Example:  $\begin{array}{ccc} & & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & \\ & & & \\ & & & \\ & & & \\ & & & \\ & & \\ & & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & &$ 

#### ■In case of error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	•

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example:

e0
e1
In case of Parameter Error:  $010100000B \Rightarrow 50h \Rightarrow 35h 30h$ In case of Mode Error:  $10010000B \Rightarrow 90h \Rightarrow 39h 30h$ 

	•
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

# 9.32 Gain Assignment

Camera Control Command Type 2

Function	Assign the camera gain						
Command	01AEh	01AEh					
Parameter	Length	Length 1 byte					
	Range	0~5 (0h~5h)					
Status	None	None					
Reference	•See the following table for relation between Parameter value and Gain value.						
	•Switching ena	abled when the shooting mode is set to <b>Manual mode</b> .					

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	AEh	p0	EFh
				$\downarrow$		

The camera gain parameter value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter.					
Example:	_			p0	
	3	$\Rightarrow$	3h	33h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example				e0	e1		
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h		
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h		
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h		

# • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is other than <b>Manual mode</b> .
	•In status Color bar output is <b>ON</b>

# • Gain Value Table

Parameter Value	Gain Value				
Parameter value	XU-80	XU-81			
00h	0dB	0dB			
01h	6dB	6dB			
02h	12dB	12dB			
03h	18dB	18dB			
04h	24dB	24dB			
05h	32dB	42dB			

### 9.33 Gain Status Request

Camera Control Command Type 1

Function	Return the camera gain status information					
Command	01C5h					
Parameter	Length	Length 1 byte				
	Value 4h					
Status	Length 1 byte					
	Range	Range 0 to 5 (0h to 5h)				
Reference	• For the detailed relation between the status and the camera gain status value,					
	refer to Camero	a Gain Status Value Table below.				

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	C5h	34h	EFh

### Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Error Code		Status	End mark
FEh	30h	30h	30h	30h	s0	EFh
				- 11		

#### ■In case of error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				11	

 Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

 Example:
 e0
 e1

 ■ In case of Parameter Error: 010100000B ⇒ 50h ⇒ 35h 30h

 ■ In case of Mode Error: 10010000B ⇒ 90h ⇒ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# • Camera Gain Status Value Table

S0	Gain Status				
30	XU-80	XU-81			
30h	0dB	0dB			
31h	6dB (2 to 6dB)	6dB (2 to 6dB)			
32h	12dB (8 to 12dB)	12dB (8 to 12dB)			
33h	18dB (14 to 18dB)	18dB (14 to 18dB)			
34h	24dB (20 to 24dB)	24dB (20~24dB)			
35h	32dB (26 to 32dB)	42dB (26 to 42dB)			

# 9.34 Gain Details Specification

Camera Control Command Type 2

Function	Set the camera	Set the camera gain.					
Command	019Eh	019Eh					
Parameter	Length	Length 2 byte					
	Range XU-80: 0 to 16 (00h to 10h)						
	_	XU-81: 0 to 21 (00h to 15h)					
Status	None						
Reference	•See the following table for relation between Parameter value and Gain value.						
	•Switching ena	abled when the shooting mode is set to <b>Manual mode</b> .					

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device	Device Num		Command		Parameter	
FFh	30h	30h	01h	9Eh	p0	p1	EFh
				TI .			

The camera gain parameter value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter.									
Example:					p0	p1			
	$10 \Rightarrow 0Ah \Rightarrow 30h 41h$								

# Answer Format

	d0	d1	d2	d3	d4	d5
	Header	Device Num		Error	End mark	
Ī	FEh	30h	30h	e0	e1	EFh
					- II	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is other than <b>Manual mode</b> .
	•In status Color bar output is <b>ON</b>

# • Gain Value Table

D V-1	Gain Value				
Parameter Value	XU-80	XU-81			
00h	0dB	0dB			
01h	2dB	2dB			
02h	4dB	4dB			
03h	6dB	6dB			
04h	8dB	8dB			
05h	10dB	10dB			
06h	12dB	12dB			
07h	14dB	14dB			
08h	16dB	16dB			
09h	18dB	18dB			
0Ah	20dB	20dB			
0Bh	22dB	22dB			
0Ch	0Ch 24dB 24dB				
0Dh	26dB	26dB			
0Eh	28dB	28dB			
0Fh	30dB	30dB			
10h	32dB	32dB			
11h		34dB			
12h 13h		36dB			
	Parameter Error	38dB			
14h		40dB			
15h		42dB			

# 9.35 Gain Detailed Status Request

Camera Control Command Type 1

Function	Return the camera gain detailed status information						
Command	01C6h	01C6h					
Parameter	Length	1 byte					
	Value	0h					
Status	Length	2 byte					
	Range	XU-80: 0 to 16 (00h to 10h)					
	_	XU-81: 0 to 21 (00h to 15h)					
Reference	•See the following table for relation between Parameter value and the gain						
	value.						

## • Format of Control Code

d0	d1 d2		d0 d1		d2 d3 d4		d5	d6
Header	Device Num		Command		Parameter	End mark		
FFh	30h	30h	01h	C6h	30h	EFh		

## Answer Format

### ■In case of No error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Error Code		Gain status		End mark
FEh	30h	30h	30h	30h	s0	s1	EFh
				Ш			

Camera Gain Status indicates in Hexadecimal 2 digits and status value is its ASCII code.							
Example:				s0	s1		
	$6 dB (3) \Rightarrow$	03h	$\Rightarrow$	30h	33h		

## ■In case of error

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h 30h		e0	e1	EFh	
				Ш		

Error Flag indicates in 2 digits	Hexadecima	l and retu	ırns ASC	III code v	alue	
Example:					e0	e1
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h	30h

	8
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.36 Iris Assignment

Camera Control Command Type 2

Function	Assign the iris					
Command	01A6h					
Parameter	Length	2 byte				
	Range	0 to 255 (00h to FFh)				
Status	None					
Reference	•To be able to se	•To be able to set when the shooting mode is <b>Manual and Iris Priority</b> .				
	•Screen darkens as numerical value decreases.					
	•Screen brighter	ns as numerical value increases.				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FEh	30h	30h	01h	A6h	p0	p1	EFh
				- II			

The Iris position indicates in 2 digits Hexadecimal, and its ASCII code treats as								
the parameter.								
Example:					p0	p1		
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h		

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	•

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.			
Mode Error	Not in status of <b>Camera ON</b>			
	•The shooting mode is <b>Auto</b> , <b>Night</b> , <b>Shutter priority mode</b> .			
	•In status Color bar output is ON			

# 9.37 Number of Iris Divisions Request

Camera Control Command Type 1

Function	Return the number of iris divisions.				
Command	01C3h				
Parameter	Length 1 byte				
	Value 1h				
Status	Length 2 byte				
	Value	XU-80: 21 (15h)			
		XU-81: 17 (11h)			
Reference	•Returns the nur	mber of divisions of the iris that can actually be set in the			
	camera. Set in 256 levels with the Iris Specification command of 9.30, but				
	actually the 256 levels are assigned in equivalent intervals in levels returned				
	by this comma	nd.			

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	Device Num		Command		End mark
FFh	30h 30h		01h	C3h	31h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Error Code		Number of iris		End mark
					divisions		
FEh	30h	30h	30h	30h	s0	s1	EFh
				П			

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example				e0	e1		
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h		
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.38 Iris Position Request

Camera Control Command Type 1

Function	Return the present iris position				
Command	01C3h				
Parameter	Length	1 byte			
	Value	2h			
Status	Length	2 byte			
	Range	XU-80: 0 to 20 (00h to 14h)			
		XU-81: 0 to 16 (00h to 10h)			
Reference	• To return the value within the number of iris divisions received by <b>9.31 Iris</b>				
	Divisions Request command as status.				

### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C3h	32h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d7	
Header	Device Num		Error Code		Number of iris		End mark	
					status			
FEh	30h	30h	30h	30h	s0	s1	EFh	
$\downarrow$								

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	End mark	
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits	Hexadecimal	and retu	ırns ASC	II code v	alue	
Example					e0	e1
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.39 Exposure Compensation Specification

Camera Control Command Type 2

Function	Compensate the exposure						
Command	01E3h						
Parameter	Length 2 byte						
	Range	0 to 255 (00h to FFh)					
Status	None						
Reference	•Can be set w	when the capturing mode is other than <b>Manual mode</b> .					
	•Screen darke	ens as numerical value decreases.					
	•Screen brigh	ntens as numerical value increases.					
	•The default	value is 128 (80h) at the moment of <b>Camera Reset</b> and <b>Camera</b>					
	ON Comma	<b>ON</b> Commands in status of Power ON.					

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parai	neter	
FEh	30h	30h	01h	E3h	p0	p1	EFh
				Ш			

The exposure compensation value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter.							
Example:					p0	p1	
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h	

# Answer Format

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h	30h	e0	e1	EFh	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is <b>Manual mode</b> .
	•In status Color bar output is ON

## 9.40 White Balance Auto

# Camera Control Command Type 2

Function	Set the white balance to auto				
Command	01A7h				
Parameter	Length 1 byte.				
	Value	0h			
Status	None	None			
Reference	•To set to <b>Aut</b>	•To set to <b>Auto</b> in default value at the moment of <b>Camera Reset</b> and <b>Camera</b>			
	ON Commands in status of Power ON.				
	•Cr gain and Cb gain setting values are 128 (80h).				

### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Command		Parameter	End mark
FFh	30h	30h	01h	A7h	30h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				П	

₩

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example e0 e1							
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON
	•In case of executing <b>Shot Memory Movement</b> Command.

# 9.41 White Balance Preset

# Camera Control Command Type 2

Function	Adjust and fix the white balance			
Command	01A7h			
Parameter	Length 1 byte.			
	Value	1h		
Status	None			
Reference	•R gain and B gain setting values are 128 (80h).			
	•It takes approxi	•It takes approximately five minutes to preset the white balance.		

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	n Command		Parameter	End mark
FFh	30h	30h	01h	A7h	31h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				- II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example e0 e1							
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON
	•In case of executing <b>Shot Memory Movement</b> Command.

### 9.42 White Balance Fixed 1

## Camera Control Command Type 2

Function	Fix the white b	Fix the white balance at an indoor setting level of 3200K				
Command	01A7h	01A7h				
Parameter	Length	Length 1 byte.				
	Value	2h				
Status	None	None				
Reference	•Cr gain and C	•Cr gain and Cb gain setting values are 128 (80h).				

### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A7h	32h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h  $\Rightarrow$ 30h 30h ■ In case of Parameter Error : 50h 01010000B 35h 30h ■ In case of Mode Error : 10010000B 90h 39h 30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON
	•In case of executing <b>Shot Memory Movement</b> command.

### 9.43 White Balance Fixed 2

## Camera Control Command Type 2

Function	Fix the white	Fix the white balance at an indoor setting level of 5800K				
Command	01A7h	01A7h				
Parameter	Length	1 byte.				
	Value	3h				
Status	None					
Reference	•Cr gain and	•Cr gain and Cb gain setting values are 128 (80h).				

### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A7h	33h	EFh

### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				TII.	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h  $\Rightarrow$ 30h 30h ■ In case of Parameter Error : 50h 01010000B 35h 30h ■ In case of Mode Error : 10010000B 90h 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON
	•In case of executing <b>Shot Memory Movement</b> command.

#### 9.44 White Balance ATW

Camera Control Command Type 2

Function	Set the white balance to ATW					
Command	01A7h					
Parameter	Length	Length 1 byte.				
	Value 4h					
Status	None					
Reference	<ul> <li>Automatically</li> </ul>	•Automatically adjusts the white balance according to the video image.				
	However, the following of color changes is faster than <b>White Balance Auto</b> .					
	•Cr gain and (	Cb gain setting values are 128 (80h).				

### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A7h	34h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error:  $00h \Rightarrow$ 0000000B 30h 30h ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error : 10010000B 90h ⇒ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is ON
	•In case of executing <b>Shot Memory Movement</b> command.

## 9.45 White Balance Mode Status Request

Camera Control Command Type 1

Function	Return the present white balance mode status information						
Command	01C5h	01C5h					
Parameter	Length 1 byte						
	Value	8h					
Status	Length	1 byte					
	Range 0 to 4 (0 to 4h)						
Reference	• For the detailed relation between the status and the white balance mode						
	status, refer to White Balance Mode Status Value Table below.						

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C5h	38h	EFh

#### Answer Format

### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Error Code		Status	End mark
FEh	30h	30h	30h	30h	s0	EFh
				Ш		

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				- II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example

In case of Parameter Error:  $01010000B \Rightarrow 50h \Rightarrow 35h 30h$ In case of Mode Error:  $0010000B \Rightarrow 90h \Rightarrow 39h 30h$ 

### • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

#### • White Balance Mode Status Value Table

S0	White Balance Mode Status					
30h	Auto					
31h	Preset					
32h	Fixed 1 (Indoor)					
33h	Fixed 2 (Outdoor)					
34h	ATW					

# 9.46 Black Level Assignment (XU-81)

Camera Control Command Type 2

Function	Adjust the black level of HD-SDI signal						
Command	01E1h	01E1h					
Parameter	Length	3 byte					
	Range	1 <sup>st</sup> byte: 0 (0h)					
		1 <sup>st</sup> byte: 0 (0h) 2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
Status	None						
Reference	• The default value is 128 (80h) when <b>Camera Reset</b> and <b>Camera ON</b>						
	commands are executed in status of Power ON.						
	• HD-SDI output changes. VBS output does not change.						
	• Valid in XU-81 only. In XU-80, the parameter error is returned.						

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand	Parameter		End mark	
FFh	30h	30h	01h	E1h	30h	p0	p1	EFh
			•	$\downarrow$	•		•	

Black level specificode as the param		cates in 1	digit Hex	adecim	al, and fix	es its ASCI	Ι
Example:					p0	p1	
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h	

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# 9.47 R Gain Assignment

Camera Control Command Type 2

Function	Adjust the R Ga	Adjust the R Gain					
Command	01E1h						
Parameter	Length	3 byte					
	Range	1 <sup>st</sup> byte: 1 (1h)					
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
Status	None	None					
Reference	•Can be switche	•Can be switched when the white balance is <b>Preset</b> .					
	•Default value v	when white balance is <b>Preset</b> is 128 (80h).					

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand	Parameter		End mark	
FFh	30h	30h	01h	E1h	31h	p0	p1	EFh
				TI .				

The R Gain value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter value.							
Example:					p0	p1	
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example				e0	e1	
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h	
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h	
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h	

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The white balance is other than <b>Preset</b> .
	•In status IR Filter is OFF
	•In status Color bar output is ON

# 9.48 B Gain Assignment

Camera Control Command Type 2

Function	Adjust the B Ga	Adjust the B Gain					
Command	01E1h						
Parameter	Length	3 byte					
	Range	1 <sup>st</sup> byte: 3 (3h)					
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
Status	None	None					
Reference	•Can be switched when white balance is <b>Preset</b> .						
	•Default value v	when white balance is <b>Preset</b> is 128 (80h).					

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand	Parameter		End mark	
FFh	30h	30h	01h	E1h	33h	p0	p1	EFh
	•			П		•		

The R Gain value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter value.							as
Example:	64	$\Rightarrow$	40h	$\Rightarrow$	p0 34h	p1 30h	

## Answer Format

d0	d1	d2	d3	d4	d5	
Header	Device	Device Num		Error Code		
FEh	30h	30h	e0	e1	EFh	
				П		

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The white balance is other than <b>Preset</b> .
	•In status IR Filter is OFF
	•In status Color bar output is ON

# 9.49 Cr Gain Assignment

Camera Control Command Type 2

Function	Adjust the Cr Gain			
Command	01E1h			
Parameter	Length	3 byte		
	Range	1 <sup>st</sup> byte: 4 (4h) 2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)		
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)		
Status	None			
Reference	•The default value is 128 (80h) at the moment of <b>Camera Reset</b> and <b>Camera</b>			
	<b>ON</b> commands in status of Power ON.			

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand		Parameter	•	End mark
FFh	30h	30h	01h	E1h	34h	p0	p1	EFh
		•	•	П			•	

The Cr Gain value indicate the parameter value.	ates in 1	digit He	exadecima	ıl, and it	s ASCII c	ode treats a	ıs
Example:	64		40h		p0 34h	p1 30h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				II	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status IR Filter is OFF
	•In status Color bar output is ON

# 9.50 Cb Gain Assignment

Camera Control Command Type 2

Function	To adjust Cb gain						
Command	01E1h						
Parameter	Length	Length 3 byte					
	Range	Range 1 <sup>st</sup> byte: 6 (6h)					
		1 <sup>st</sup> byte: 6 (6h) 2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
Status	None						
Reference	•The default value is 128 (80h) at the moment of <b>Camera Reset</b> and <b>Camera</b>						
	ON command	s in status of Power ON.					

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Command		Parameter			End mark
FFh	30h	30h	01h	E1h	36h	p0	p1	EFh
	•	•		П	•	•	•	

The Cb Gain value in the parameter value.	dicates in 1	l digit He	exadecima	al, and it	ts ASCII o	code treats as
Example:					p0	p1
	64	$\Rightarrow$	40h	$\Rightarrow$	34h	30h

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				- II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example				e0	e1		
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h		
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h		
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status IR Filter is OFF
	•In status Color bar output is ON

# 9.51 Edge Assignment

Camera Control Command Type 2

Function	Adjust the video edges						
Command	01E1h						
Parameter	Length	Length 3 byte					
	Range	1 <sup>st</sup> byte: 10 (Ah) 2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 255 (0h to FFh)					
Status	None	None					
Reference	•The default value is 128 (80h) at the moment of <b>Camera Reset</b> and <b>Camera</b>						
	ON commands	s in status of Power ON.					

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Command		Parameter			End mark
FFh	30h	30h	01h	E1h	41h	p0	p1	EFh
				П		•		

The edge compensation value indicates in 1 digit Hexadecimal, and its ASCII code treats as the parameter value.							
Example:	64	$\rightarrow$	40h	$\rightarrow$	p0 34h	p1 30h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example				e0	e1		
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h		
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h		
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h		

Parameter Error	•Assigned parameter is an invalid value.			
Mode Error	Not in status of Camera ON			
	•In status Color bar output is ON			

# **9.52 WDR OFF**

# Camera Control Command Type 2

Function	Turn off the Wide Dynamic Range						
Command	01A5h						
Parameter	Length	Length 1 byte.					
	Value	0h					
Status	None	None					
Reference	•This command is selected by default at the moment of <b>Camera Reset</b> and						
	Camera ON	Camera ON commands in status of Power ON.					

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A5h	30h	EFh

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value								
Example					e0 e1			
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h			
■ In case of Parameter Error:	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h			
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h			

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

## 9.53 WDR ON

## Camera Control Command Type 2

Function	Turn on the Wid	Turn on the Wide Dynamic Range					
Command	01A5h	01A5h					
Donomoton	Length	1 byte.					
Parameter	Value	1h					
Status	None						
Reference							

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	A5h	31h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				H	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h  $\Rightarrow$ 30h 30h ■ In case of Parameter Error : 01010000B 50h 35h 30h ■ In case of Mode Error : 10010000B90h 39h 30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

## 9.54 WDR Status Request

Camera Control Command Type 1

Function	Return the present Wide Dynamic Range status information					
Command	01C5h	01C5h				
Parameter	Length	1 byte				
	Value	7h				
Status	Length	1 byte				
	Range	Range 0, 1 (0h to 1h)				
Reference	• For the detailed relation between the status and the Wide Dynamic Range					
	status, refer to	status, refer to Wide Dynamic Range Status Value Table below.				

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Devic	Device Num		Command		End mark
FFh	30h	30h	01h	C5h	37h	EFh

#### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Error Code		Status	End mark
FEh	30h	30h	30h	30h	s0	EFh
				Ш		

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				11	

 Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

 Example
 e0
 e1

 ■ In case of Parameter Error: 01010000B ⇒ 50h ⇒ 35h 30h

 ■ In case of Mode Error: 10010000B ⇒ 90h ⇒ 39h 30h

## • Condition of Error flag to be set

	9
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

## • Wide Dynamic Range Status Value Table

S0	Wide Dynamic Range Status
30h	OFF
31h	ON

#### 9.55 ND Filter OFF

Camera Control Command Type 2

Function	Turn off the ND filter					
Command	01B6h					
Parameter	Length	1 byte.				
	Value	Value 0h				
Status	None	None				
Reference	•Returns command error when no outdoor options are installed.					
	•This command is selected by default at the moment of <b>Camera Reset</b> and					
	<b>Camera ON</b> commands in status of Power ON.					

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	B6h	30h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				- III	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B  $00h \Rightarrow$ 30h 30h ■ In case of Busy Error: 00010000B 10h  $\Rightarrow$ 31h 30h ■ In case of Command Error: 00110000B  $30h \Rightarrow$ 33h 30h ■ In case of Parameter Error : 50h ⇒ 01010000B 35h 30h ■ In case of Mode Error: 10010000B 90h  $\Rightarrow$ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Busy Error	•In case of executing <b>Shot Memory Movement</b> Command.
	•When executing the pan movement operation with the pan-tilt
	control command.
	•When executing the tilt movement operation with the pan-tilt
	control command.
	•When executing Wiper Control and Washer Control command.
Command Error	•When no outdoor options are installed.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is ON

#### 9.56 ND Filter ON

Camera Control Command Type 2

Function	Turn on the N	Turn on the ND filter				
Command	01B6h	01B6h				
Parameter	Length	1 byte.				
	Value 1h					
Status	None					
Reference	•Returns command error when no outdoor options are installed.					

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	B6h	31h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h  $\Rightarrow$ 30h 30h  $\Rightarrow$ ■ In case of Busy Error: 00010000B 10h 31h 30h ■ In case of Command Error: 30h 00110000B 33h 30h  $\Rightarrow$ ■ In case of Parameter Error : 01010000B  $50h \Rightarrow$ 35h 30h ■ In case of Mode Error: 10010000B 90h 39h 30h

	8
Parameter Error	•Assigned parameter is an invalid value.
Busy Error	•In case of executing <b>Shot Memory Movement</b> Command.
	•When executing the pan movement operation with the pan-tilt
	control command.
	•When executing the tilt movement operation with the pan-tilt
	control command.
	•When executing Wiper Control and Washer Control command.
Command Error	•When no outdoor options are installed.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is ON

## 9.57 ND Status Request

Camera Control Command Type 1

Function	Return the present ND filter status information				
Command	01C5h				
Parameter	Length 1 byte				
	Value	0h			
Status	Length 1 byte				
	0, 1, 15 (0h, 1h, Fh)				
Reference	• For the detaile	d relation between the status and the ND status, refer to FD			
	Filter Status V	Value Table below.			
	•When outdoor options are not installed, the validity of function can be known				
	since No Function is returned. Therefore the command can be received even				
	in case Camera Power OFF.				

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	
Header	Device Num		Com	Command		End mark	
FFh	30h 30h		01h	C5h	30h	EFh	

#### Answer Format

#### ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Error Code		Status	End mark
FEh	FEh 30h 30h		30h	30h	s0	EFh
				ll		

ND Filter status value indicates in 1 digit Hexadecimal, and fixes its ASCII code as the status value.

Example:  $1 \Rightarrow 1h \Rightarrow 31h$ 

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				- 11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example e0 e1

■ In case of Parameter Error: 01010000B ⇒ 50h ⇒ 35h 30h

## • Condition of Error flag to be set

Parameter Error •Assigned parameter is an invalid value.

#### • ND Filter Status Value Table

S0	ND Filter Status
30h	OFF
31h	ON
46h	No Function

# 9.58 IR Filter OFF

# Camera Control Command Type 2

Function	Turn off the IR filter (ICR ON)						
Command	01BBh	01BBh					
Parameter	Length 1 byte.						
	Value	Oh					
Status	None	None					
Reference	•Video automatically becomes black and white.						

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h 30h		01h	BBh	30h	EFh

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

	· ·							
Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value								
Example					e0 e1			
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h			
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h			
■ In case of Mode Error :	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h			

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

## 9.59 IR Filter ON

## Camera Control Command Type 2

Function	To turn on the IR filter (ICR OFF)				
Command	01BBh				
Parameter	Length 1 byte.				
	Value	1h			
Status	None				
Reference	•This command	is selected by default at the moment of <b>Camera Reset</b> and			
	Camera ON c	Camera ON commands in status of Power ON.			
	<ul> <li>Video automat</li> </ul>	ically becomes color.			

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h 30h		BBh	31h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 0000000B 00h 30h 30h ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error: 10010000B 90h 39h 30h

Parameter Error	Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# 9.60 IR Filter Status Request

Camera Control Command Type 1

Function	Return the prese	Return the present IR filter status information				
Command	01C5h	01C5h				
Parameter	Length 1 byte					
	Value	Bh				
Status	Length	1 byte				
	Range	0 to 1 (0 to 1h)				
Reference	• For the detailed relation between the status and the IR Filter status, refer to					
	IR Filter Status Value Table below.					

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	C5h	42h	EFh

## Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Error Code		Status	End mark
FEh	30h	30h	30h	30h	s0	EFh

IR Filter status value indicates in 1 digit Hexadecimal, and fixes its ASCII code						
as the status value.						
Example:					s0	
	1	$\Rightarrow$	1h	$\Rightarrow$	31h	

## ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				- 11	

Error Flag indicates in 2 digit	s Hexadecimal and	returns AS	CII cod	e value	
Example				e0	e1
■ In case of Parameter Error	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

## • IR Filter Status Value Table

S0	IR Filter Status
30h	IR Filter OFF
31h	IR Filter ON

## 9.61 Auto IR OFF

Camera Control Command Type 2

Function	Turn off the auto IR filter					
Command	01BAh	01BAh				
Parameter	Length	1 byte.				
	Value 0 (0h)					
Status	None					
Reference	•This command is selected by default at the moment of <b>Camera Reset</b> and					
	Camera ON Commands in status of Power ON.					
	•This command is selected by default at the moment of the shooting mode					
	changes to mod	le other than Night mode.				

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	BAh	30h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example

In case of No Error:

00000000B ⇒ 00h ⇒ 30h 30h

In case of Parameter Error:

01010000B ⇒ 50h ⇒ 35h 30h

In case of Mode Error:

10010000B ⇒ 90h ⇒ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is other than <b>Night mode</b> .
	•In status Color bar output is ON

## 9.62 Auto IR ON (Slow Shutter)

## Camera Control Command Type 2

Function	Turn on the auto IR filter (slow shutter)				
Command	01BAh				
Parameter	Length 1 byte.				
	Value	1 (1h)			
Status	None				
Reference	•Can be switche	ed when shooting mode is <b>Night mode</b> .			
	•When camera a	gain is maxed, and the periphery becomes dark until the slow			
	shutter reaches	the lower limit value, <b>IR filter</b> automatically turns <b>off</b> . For			
	that reason, eve	en if the slow shutter is entered, there is an effect if you want			
	to get color video.				
	•When the periphery becomes brighter, the <b>IR filter</b> automatically turns <b>on</b> .				
	•This command is selected by default at the moment of shooting mode				
	changes to <b>Night mode</b> .				
	•Cannot be operated if the AE maximum gain setting is lower than 21 dB.				

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	BAh	31h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				- II	•

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 00h 30h 30h 0000000B  $\Rightarrow$ ■ In case of Parameter Error : 01010000B 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error : 10010000B 90h 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is other than <b>Night mode</b> .
	•The AE maximum gain setting is lower than 21 dB.
	•In status Color bar output is ON

# 9.63 Auto IR ON (Gain)

# Camera Control Command Type 2

Function	Turn on the auto IR filter (gain)					
Command	01BAh					
Parameter	Length 1 byte.					
	Value	2 (2h)				
Status	None					
Reference	•Can be switched when shooting mode is <b>Night mode</b> .					
	•When camera gain is maxed, slow shutter changes from 1/30 to 1/15, and the					
	periphery becomes dark, <b>IR filter</b> automatically turns <b>off</b> . For that reason,					
	even if the video is black and white, there is an effect if you want to get video					
	with emphasis on movement.					
	•When the periphery becomes brighter, the <b>IR filter</b> automatically turns <b>on</b> .					
	•Cannot be operated if the <b>AE maximum gain setting</b> is lower than 21 dB.					

# • Format of Control Command

	d0	d1	d2	d3	d4	d5	d6
	Header	Device Num		Command		Parameter	End mark
ſ	FFh	30h	30h	01h	BAh	32h	EFh

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value							
Example					e0 e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h 30h		
■ In case of Parameter Error :	01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h 30h		
■ In case of Mode Error:	10010000B	$\Rightarrow$	90h	$\Rightarrow$	39h 30h		

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•The shooting mode is other than <b>Night mode</b> .
	•The AE maximum gain setting is lower than 21 dB.
	•In status Color bar output is ON

## 9.64 Auto IR Status Request

Camera Control Command Type 1

Function	Return the prese	Return the present auto IR status information						
Command	01C5h							
Parameter	Length	ength 1 byte						
	Value	Ah						
Status	tatus Length 1 byte							
	Range	0 to 2 (0 to 2h)						
Reference	• For the detailed relation between the status and the Auto IR mode status,							
	refer to Auto I	refer to Auto IR Mode Status Value Table below.						

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	C5h	41h	EFh

#### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6				
Header	Device Num		Error Code		Status	End mark				
FEh	30h	30h	30h	30h	s0	EFh				
TI T										

Auto IR mode status value indicates in 1 digit Hexadecimal, and fixes its ASCII code as the status value.

Example:  $1 \Rightarrow 1h \Rightarrow 31h$ 

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				- II	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example e0 e1

In case of Parameter Error:  $01010000B \Rightarrow 50h \Rightarrow 35h 30h$ In case of Mode Error:  $10010000B \Rightarrow 90h \Rightarrow 39h 30h$ 

## • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

## • Auto IR Mode Status Value Table

S0	Auto IR Mode Status
30h	OFF
31h	ON (Slow Shutter)
32h	ON (Gain)

## 9.65 GENLOCK Vertical Line Information Request

Camera Control Command Type 1

Function	Return the GEN	Return the GENLOCK vertical line information					
Command	01C7h	01C7h					
Parameter	Length	1 byte					
	Value	0h					
Status	Length	4 byte					
	Range	0 to 15 (0000h to 000Fh)					
Reference							

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Com	mand	Parameter	End mark
FFh	30h 30h		01h	C7h	30h	EFh

### Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d6	d7	d8	
Header	Device Num		Error	Error Code		Phases Information				
neadei			Error Code			mark				
FEh	30h	30h	30h	30h	s0	s1	s2	s3	EFh	
11										

GENLOCK vertical phase value indicates in 2 digits Hexadecimal, and fixes its ASCII code as the status value.

Example:

s0 s1 s2 s3

4 ⇒ 0004h ⇒ 30h 30h 30h 34h

### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value

Example e0 e1

In case of Parameter Error:  $01010000B \Rightarrow 50h \Rightarrow 35h 30h$ In case of Mode Error:  $10010000B \Rightarrow 90h \Rightarrow 39h 30h$ 

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 9.66 GENLOCK Horizontal Phases Information Request

Camera Control Command Type 1

		<b>71</b>						
Function	Return the GEN	Return the GENLOCK horizontal phases information						
Command	01C7h	1C7h						
Parameter	Length	1 byte						
	Value	1h						
Status	Length	4 byte						
	Range	1080 60i: 0 to 2199 (0000h to 0897h)						
	_	1080 50i: 0 to 2639 (0000h to 0A4Fh)						
		720 60p:0 to 1649 (0000h to 0671h)						
		720 50p: 0 to 1979 (0000h to 07BBh)						
Reference	•The status rang	ge is changed by the video rate and video format settings as						
shown above.								

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h 30h		01h C7h		31h	EFh

## Answer Format

## ■ In case of no Error

d0	d1	d2	d3	d4	d5	d6	d6	d7	d8	
Header	Dovio	e Num	Error	Codo		Dhagag In	formation		End	
пеацеі	Device	e Mulli	EHOI	Error Code		Phases Information				
FEh	30h	30h	30h	30h	s0	s1	s2	s3	EFh	
				11						

GENLOCK Horizontal Phases indicates in 2 digits Hexadecimal, and fixes its ASCII code as the status value.

Example:

\$ s0 \$ s1 \$ s2 \$ s3 \$ 324 \$ \Rightarrow 0144h \Rightarrow 30h 31h 34h 34h \$ 34h

## ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example				e0	e1	
■ In case of Parameter Error:	01010000B ⇒	50h	$\Rightarrow$	35h	30h	
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h	

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

## 10. Details of Camera Setting Command

# 10.1 AE Area Setting

## Camera Control Command Type 2

Function	Set the AE judg	Set the AE judgment area			
Command	01BDh	1BDh			
Parameter	Length	2 byte			
	Range	1 <sup>st</sup> byte: 1 (1h) 2 <sup>nd</sup> byte: 0 to 11 (0h to Bh)			
		2 <sup>nd</sup> byte: 0 to 11 (0h to Bh)			
Status	None	None			
Reference	•Saves the statu	•Saves the status even after pan-tilt is reset.			
	•Do not operate	•Do not operate anything other than the camera settings for three seconds after			
	making these settings.				
	<ul> <li>Factory default</li> </ul>	setting is "normal".			

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FEh	30h	30h	01h	BDh	31h	p0	EFh

## Answer Format


d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				11	


Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of No Error: 30h 30h  $00000000B \Rightarrow$ 00h ■ In case of Parameter Error:  $01010000B \Rightarrow$ 50h  $\Rightarrow$ 35h 30h ■ In case of Mode Error:  $10010000B \Rightarrow$ 90h 39h 30h  $\Rightarrow$ 

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# • AE Area Table

Parameter Value	AE Area
00h	Narrow
01h	Normal
02h	Wide
03h	Aria 1
04h	Aria 2
05h	Aria 3
06h	Aria 4
07h	Aria 5
08h	Aria 6
09h	Aria 7
0Ah	Aria 8
0Bh	Aria 9





# 10.2 AE Responsiveness Setting

# Camera Control Command Type 2

Function	Set the AE resp	Set the AE responsiveness			
Command	01BDh	)1BDh			
Parameter	Length 2 byte				
	Range 1 <sup>st</sup> byte : 2 (2h) 2 <sup>nd</sup> byte : 0 to 2 (0h to 2h)				
		2 <sup>nd</sup> byte: 0 to 2 (0h to 2h)			
Status	None				
Reference	•Saves the statu	•Saves the status even after pan-tilt is reset.			
	•Do not operate	•Do not operate anything other than the camera settings for three seconds after			
	making these settings.				
	•Factory defaul	It setting is "normal".			

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	BDh	32h	p0	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

	0
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON
	•In status Color bar output is ON

## • AE Area Table

Parameter Value	AE Area
00h	Slow
01h	Normal
02h	Fast

# 10.3 AE Maximum Gain Setting

Camera Control Command Type 2

Function	Set the AE maximum gain					
Command	01BDh					
Parameter	Length	2 byte				
	Range	1 <sup>st</sup> byte : 3 (3h)				
		2 <sup>nd</sup> byte: XU-80:0 to 7 (0h to 7h)				
	XU-81: 0 to 9 (0h to 9h)					
Status	None					
Reference	•Saves the status even after pan-tilt is reset.					
	•Do not operate anything other than the camera settings for three seconds after					
	making these settings.					
	•Factory default	setting is "32dB" (XU-80) or "42dB" (XU-81).				

#### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	
Header	Device Num		Command		Parameter		End mark	
FFh	30h	30h	01h	BDh	33h	p0	EFh	

#### Answer Format

d0	d1	d1 d2 d3 d4		d5	
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of No Error:  $00000000B \Rightarrow$ 00h  $\Rightarrow$ 30h 30h ■ In case of Parameter Error:  $01010000B \Rightarrow$  $\Rightarrow$ 50h 30h 35h ■ In case of Mode Error:  $10010000B \Rightarrow$ 90h  $\Rightarrow$ 39h 30h

## • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

## ● AE Area Table

Parameter Value	AE Maximum Gain			
Parameter value	XU-80	XU-81		
00h	0 db	0 db		
01h	3 db	3 db		
02h	6 db	6 db		
03h	12 db	12 db		
04h	17 db	17 db		
05h	21 db	21 db		
06h	26 db	26 db		
07h	32 db	30 db		
08h	Parameter Error	36 db		
09h	i arameter Enor	42 db		

# 10.4 Brightness Peak Compression (XU-81)

## Camera Control Command Type 2

Function	Adjust the brightness peak compression level at AE					
Command	01F0h					
Parameter	Length	3 byte				
	Range	1 <sup>st</sup> byte: 1 (1h)				
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 16 (0h to 10h)				
Status	None					
Reference	•Can be used as the support of exposure compensation since the total					
	brightness is also adjusted.					
	•Saves the status even after pan-tilt is reset.					
	•Do not operate anything other than the camera settings for three seconds after					
	making these settings.					
	•Factory default	•Factory default setting is "6".				
	•Valid only in X	XU-81. In XU-80, command error is returned.				

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Davia	e Num	Com	mand		Parameter		End
neadei	Devic	e Mulli	Colli	mand		Parameter		mark
FFh	30h	30h	01h	F0h	31h	p0	P1	EFh
				- 11				

Brightness Peak Compression value indicates in 1 digit Hexadecimal, and fixes its ASCII code as the parameter value.

Example:  $\begin{array}{ccc} s0 & s1 \\ 2 & \Rightarrow & 02h & \Rightarrow & 30h & 32h \end{array}$ 

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h 30h		e0	e1	EFh
				Ш	•

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error	: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# 10.5 AF Area Setting

# Camera Control Command Type 2

Function	Set the AF judg	Set the AF judgment area		
Command	01BDh			
Parameter	Length	2 byte		
	Range	1 <sup>st</sup> byte: 4 (4h) 2 <sup>nd</sup> byte: 0 to 11 (0h to Bh)		
	2 <sup>nd</sup> byte: 0 to 11 (0h to Bh)			
Status	None			
Reference	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after			
	making these settings.			
	•Factory default	setting is "narrow".		

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	er Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	BDh	34h	p0	EFh

## Answer Format


d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				JĮ.	


Error Flag indicates in 2 digits	s Hexadecimal and	returns AS	CII cod	le value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error	:: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.	
Mode Error	•Not in status of <b>Camera ON</b>	
	•In status Color bar output is ON	

# • AF Area Table

Parameter Value	AF Area
00h	Narrow
01h	Normal
02h	Wide
03h	Area 1
04h	Area 2
05h	Area 3
06h	Area 4
07h	Area 5
08h	Area 6
09h	Area 7
0Ah	Area 8
0Bh	Area 9





# 10.6 AF Sensitivity Setting

# Camera Control Command Type 2

Function	Set the AF sens	Set the AF sensitivity		
Command	01BDh			
Parameter	Length	2 byte		
	Range	1 <sup>st</sup> byte : 5 (5h) 2 <sup>nd</sup> byte : 0 to 1 (0h to 1h)		
	2 <sup>nd</sup> byte: 0 to 1 (0h to 1h)			
Status	None			
Reference	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after			
	making these settings.			
	<ul> <li>Factory defaul</li> </ul>	t setting is "normal".		

## • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	er Device Num		Command		Parameter		End mark
FEh	30h	30h	01h	BDh	35h	p0	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

	0	
Parameter Error	•Assigned parameter is an invalid value.	
Mode Error	•Not in status of Camera ON	
	•In status Color bar output is ON	

# ● AF Sensitivity Table

Parameter Value	AF Sensitivity
00h	Low
01h	Normal

# 10.7 AWB Shift Setting

# Camera Control Command Type 2

Function	Adjust the shift amount when using AWB			
Command	01BDh			
Parameter	Length	2 byte		
	Range	1 <sup>st</sup> byte : 6 (6h) 2 <sup>nd</sup> byte : 0 to 6 (0h to 6h)		
	_	2 <sup>nd</sup> byte: 0 to 6 (0h to 6h)		
Status	None			
Reference	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after			
	making these settings.			
	<ul> <li>Factory defaul</li> </ul>	t setting is "normal".		

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FEh	30h	30h	01h	BDh	36h	p0	EFh

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII co	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# • AWB Shift Table

Parameter Value	AE Shift
00h	Normal
01h	R-Low
02h	R-Middle
03h	R-High
04h	B-Low
05h	B-Middle
06h	B-High

# 10.8 Gamma Level Setting

Camera Control Command Type 2

Function	Set the gamma level				
Command	01F2h				
Parameter	Length	1 byte			
	Range	XU-80: 0 to 4 (0h to 4h)			
		XU-81: 0 to 5 (0h to 5h)			
Status	None	None			
Reference	•Saves the st	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after				
	making these settings.				
	•Factory defa	ault setting is "0.6"(XU-80) or "0.45"(XU-81).			

# • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	F2h	p0	EFh
				Ш		

The Gamma parameter value indicates in 1 digit Hexadecimal, and its ASCII						
code treats as	the parar	neter.				
Example:					p0	
	3	$\Rightarrow$	3h	$\Rightarrow$	33h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				11	•

Error Flag indicates in 2 digit	ts Hexadecimal and r	eturns AS	SCII cod	e value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

# • Condition of Error flag to be set

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# • Gamma Level Table

Parameter	Gamm	a Level
Parameter	XU-80	XU-81
00h	0.3	0.3
01h	0.45	0.45
02h	0.6	0.6
03h	0.8	0.8
04h	1.0	1.0
05h	Parameter Error	0.525
06h to 08h	Parameter Effor	Reserve

# 10.9 Contrast Adjustment (XU-81)

# Camera Control Command Type 2

Function	Adjust the video contrast				
Command	01F0h				
Parameter	Length 3 byte				
	Range	1 <sup>st</sup> byte: 2 (2h)			
		2 <sup>nd</sup> , 3 <sup>rd</sup> byte: 0 to 16 (0h to 10h)			
Status	None				
Reference	•When the se	•When the setting value is big, the low brightness part may be blackened.			
	•Saves the st	atus even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after				
	making these settings.				
	•Factory def	ault setting is "3".			
	•Valid only i	in XU-81. In XU-80, command error is returned.			

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device Num		Command		Parameter			End
Header	Devic	e Ivulli	Colli	manu		rarameter		mark
FFh	30h	30h	01h	F0h	32h	p0	P1	EFh
		•		$\downarrow$	•		•	•

Contrast Adjustment value indicates in 1 digit Hexadecimal, and fixes its ASCII							
code as the p	arameter va	ılue.					
Example:					s0	s1	
_	2	$\Rightarrow$	02h	$\Rightarrow$	30h	32h	

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				ll l	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example				e0	e1	
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h	
■ In case of Parameter Error:	$01010000B \Rightarrow$	50h	$\Rightarrow$	35h	30h	
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h	

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>
	•In status Color bar output is ON

# 10.10 TV Setup OFF

## Camera Control Command Type 2

Function	Turn off the composite signal TV setup				
Command	01E1h				
Parameter	Length	Length 3 byte			
	Range	1 <sup>st</sup> byte: 11 (Bh)			
		2 <sup>nd</sup> byte: 0 (0h) 3 <sup>rd</sup> byte: 0 (0h)			
		3 <sup>rd</sup> byte: 0 (0h)			
Status	None				
Reference	•Saves the star	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after				
	making these	making these settings.			
	•Factory defau	alt setting is "ON".			

#### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Com	mand		Parameter	•	End mark
FFh	30h	30h	01h	E1h	42h	30h	30h	EFh

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	Code	End mark
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of No Error:  $00000000B \Rightarrow$ 00h  $\Rightarrow$ 30h 30h ■ In case of Parameter Error:  $01010000B \Rightarrow$ 50h 30h  $\Rightarrow$ 35h ■ In case of Mode Error:  $10010000B \Rightarrow$ 90h  $\Rightarrow$ 39h 30h

	0
Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 10.11 TV Setup ON

# Camera Control Command Type 2

Function	Turn on the composite signal TV setup			
Command	01E1h			
Parameter	Length	3 byte		
	Range	1 <sup>st</sup> byte: 11 (Bh)		
		2 <sup>nd</sup> byte: 0 (0h) 3 <sup>rd</sup> byte: 1 (1h)		
		3 <sup>rd</sup> byte : 1 (1h)		
Status	None	None		
Reference	•If the video sig	nal setting is 59.94i, the video black level output from the		
	VBS pin rises	7.5%.		
	•Saves the status even after pan-tilt is reset.			
	•Do not operate anything other than the camera settings for three seconds after			
	making these s	making these settings.		
	•Factory default	setting is "ON".		

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device Num		Command		Parameter			End mark
FFh	30h	30h	01h	E1h	42h	30h	31h	EFh

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh 30h		30h	e0	e1	EFh
				П	

Error Flag indicates in 2 digit	s Hexadecimal and r	eturns AS	SCII cod	e value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Erro	r: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	$10010000B \Rightarrow$	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of Camera ON

## 10.12 GENLOCK Phases Relative Value Adjustment

Camera Control Command Type 2

Function	Adjust the GENLOCK phase										
Command	01E4h										
Parameter	Length	Length 2 byte									
	Range	0 to 255 (00h to FFh)									
Status	None	None									
Reference	change the vide •Do not operate making these se •Parameter indic adjusting GEN- GENLOCK ph Example: To ad	cates the relative value considering 80h as a median for LOCK phase. Effective in fine-adjustments of the									

#### • Format of Control Command

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parameter		End mark
FFh	30h	30h	01h	E4h	p0	p1	EFh
					11		

The GEN-LOCK Phase Adjustment value indicates in 2 digits Hexadecimal, and its ASCII code treats as the parameter value.

Example: p0 p1 158  $\Rightarrow$  9Eh  $\Rightarrow$  39h 45h

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	FEh 30h		e0	e1	EFh

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0 e1 ■ In case of No Error: 00000000B ⇒ 00h 30h 30h  $\Rightarrow$ ■ In case of Parameter Error:  $01010000B \Rightarrow$ 50h 35h 30h  $\Rightarrow$ ■ In case of Mode Error:  $10010000B \Rightarrow$ 90h  $\Rightarrow$ 39h 30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 10.13 GENLOCK Phases Absolute Value Adjustment

Camera Control Command Type 2

Function	Adjust the GENLOCK phase								
Command	01E7h								
Parameter	Length	8 byte							
	Range	Vertical:		0 to 15 (0000h to 000Fh)					
	_	Horizontal	(1080 60i):	0 to 2199 (0000h to 0897h)					
			(1080 50i):	0 to 2639 (0000h to 0A4Fh)					
			(720 60p):	0 to 1649 (0000h to 0671h)					
			(720 50p):	0 to 1979 (0000h to 07BBh)					
Status	None								
Reference	•Saves the status	s even after j	pan-tilt is rese	t. However, this changes when you					
	change the vide	o rate and v	ideo format se	etting.					
	•Do not operate	anything oth	ner than the ca	mera settings for three seconds after					
	making these so	ettings.							
	•Parameter displ	ays the abso	olute value to a	adjust GENLOCK phase.					
	•The horizontal	parameter ra	inge is change	d by the video rate and video format					
	settings as desc	ribed above							
	•Factory default	setting is "	Vertical: 7 H	orizontal : 0".					

# • Format of Control Command

d0	d1	d2	d3	d4	
Header	Device	e Num	Command		
FFh	30h	30h	01h	E7h	

d5	d6	d7	d8	d9	d10	d11	d12	d13	
	Vertical Parameter				orizontal	End mark			
p0	p1	p2	р3	p4	p5	р6	p7	EFh	
	Ш								

The GEN-LOCK Phase Adjustment value indicates in 2 digits Hexadecimal, and								
its ASCII code treats as the parameter value.								
Example: Vertical 0010, Horizontal 2000								
Pan	p0	p1	p2	p3				
$0010 \Rightarrow 000Ah \Rightarrow$	30h	30h	30h	41h				
Tilt	p4	p5	p6	p7				
$2000 \Rightarrow 07D0h \Rightarrow$	30h	37h	44h	30h				

## Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error Code		End mark
FEh	30h	30h	e0	e1	EFh
				$\downarrow$	

Error Flag indicates in 2 digits	Hexadecimal and	returns AS	CII cod	de value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error	: 01010000B ⇒	50h	$\Rightarrow$	35h	30h
■ In case of Mode Error:	10010000B ⇒	90h	$\Rightarrow$	39h	30h

Parameter Error	•Assigned parameter is an invalid value.
Mode Error	•Not in status of <b>Camera ON</b>

# 11. Details of System Control Command

# 11.1 Operation Status Request

System Control Command Type 1

Function	Return info	Return information of inside status of the pan-tilt head (operation status)					
Command	0186h	0186h					
Parameter	None	None					
Status	Length	3 byte	3 byte				
	Value	Value of op	peration status which indicates inside status (12 bits)				
Reference	•The follow	wings show sta	atus, in case that each bit is 1 among of status.				
		(MSB)					
		b11	Tilting under operation				
		b10	Tilt movable limit position				
		b9	Panning under operation				
		b8	Pan movable limit position				
		b7	Zooming under operation				
		b6	Not used				
		b5	Camera Power OFF				
		b4	Not used				
		b3	Not used				
		b2	Not used				
		b1	Manual Focus mode				
		b0	Focusing under operation				
		(LSB)					

## • Format of Control Command

d0	d1	d2	d3	d4	d5
Header	Device Num		Com	End mark	
FFh	30h	30h	01h	86h	EFh

## Answer Format

d0	d1	d2	d3	d4	d5	d6	d7	d8
Header	Device	e Num	Error	Code		Status		End mark
FEh	30h	30h	30h	30h	s0	s1	s2	EFh
				ll				

Inside operation status (12bits) indicated camera inside status indicates in 3 digits Hexadecimal returns ASCII code as status Example: s0s1s2b11 b10 b9 b8 b7 b6 b5 **b**4 b3 **b**0 b2 b1 0 0 0 "8" "4" "0"  $\downarrow \downarrow$  $\downarrow \downarrow$ 34h 38h 30h

# 11.2 Extended Operation Status Request

System Control Command Type 1

Function	Daturn the aytan	ded information of inside status of the pan-tilt head (operation		
Tunction		status)		
Command	0186h			
Parameter	0h			
		51-4-		
Status	Length	5 byte		
	Value	value of operation status which indicates inside status		
<b>D</b> 6		(20 bits)		
Reference	_	show status, in case that each bit is 1 among of status.		
	(MS			
	b19	Not used		
l	b18	Not used		
	b17	Tilt motor error		
	b16	Pan motor error		
	b15	Not used		
	b14	Camera busy		
	b13	Camera mode MANUAL		
	b12	Other than White balance mode AUTO		
	b11	Tilting under operation		
	b10	Tilt movable limit position		
	b 9	Panning under operation		
	b 8	Pan movable limit position		
	b7	Zooming under operation		
	b6	Not used		
	b5	Camera Power OFF		
	b4	Not used		
	b3	Not used		
	b2	Not used		
	b1	Focus mode MANUAL		
	b0	Focusing under operation		
	(LSI	3)		
1	•The information	n of b0 through b11 is equal to the information of <b>10.1</b>		
	Operation Stat	tus Request.		

# • Format of Control Command

d0	d1	d2	d3	d4	d5	d6
Header	Device	e Num	Com	mand	Parameter	End mark
FFh	30h	30h	01h	86h	30h	EFh

- Answer Format
- In case of no Error

d0	d1	d2	d3	d4				
Header	Device	e Num	Error	Code				
FEh	30h	30h	30h	30h				
			d5	d6	d7	d8	d9	d10
					Status			End mark
			s0	s1	s2	s3	s4	EFh
				$\downarrow$		•	•	

Inside operation status (12bits) indicated camera inside status indicates in 5 digits Hexadecimal returns ASCII code as status Example: s0s1b19 b18 b17 b16 b15 b14 b13 b12 0 0 0 0 0 0 0 0 "0" "0"  $\downarrow \downarrow$  $\downarrow \downarrow$ 30h 30h s2s3 s4 b11 b10 b9 b8 b7 b6 b5 b4 b3 b2 b1 b0 0 0 0 0 0 0 0 1 0 0 "4" "8" "0"  $\bigcup$  $\bigcup$  $\downarrow \downarrow$ 34h 38h 30h

#### ■ In case of Error

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				Ш	

Error Flag comes out Hexadecimal 2 digits and returns ASCII value

Example e0 e1

■ In case of Parameter error 01010000B ⇒ 50h ⇒ 35h 30h

	8
Parameter Error	•Assigned parameter is an invalid value.

# 11.3 Product Name Request

System Control Command Type 1

Function	Return the produ	Return the product name			
Command	0187h	0187h			
Parameter	None	None			
Status	Length	7 byte			
	Value	"XU-80" (58h 55h 2Dh 38h 30h 20h 20h)			
Reference	To return fixed value.				

# • Format of Control Command

d0	d1	d2	d3	d4	d5
Header	Device	Device Num		mand	End mark
FFh	30h	30h	01h	87h	EFh

# • Answer Format

	0b	d1	d2	d3	d4	_			
He	ader	Device	e Num	Error	Error Code				
F	Eh	30h	30h	30h	30h				
	_	d5	d6	d7	d8	d9	d10	d11	d12
					Status				End mark
		58h	55h	2Dh	38h	30h	20h	20h	EFh

# 11.4 ROM Version Request

System Control Command Type 1

Function	Return the Ro	Return the ROM version of the pan-tilt head				
Command	0188h	0188h				
Parameter	None	None				
Status	Length	6 byte				
	Value	"V01-01" (56h 30h 31h 2Dh 30h 31h)				
Reference	Status value (Version number) may be changed in future.					

# • Format of Control Command

d0	d1	d2	d3	d4	d5
Header	Device	Device Num		mand	End mark
FFh	30h	30h	01h	88h	EFh

# Answer Format

d0	d1	d2	d3	d4	_				
Header	Device	e Num	Error	Code					
FEh	30h	30h	30h	30h					
		d5	d6	d7	d8	d9	d10	d11	
			Status F						
		56h	30h	31h	2Dh	30h	31h	EFh	

# 11.5 Zoom, Focus, Tilt, and Pan Speed Control Assignment

System Control Command Type 2

Function	Operate at the assigned zooming, focusing, tilting, and panning speeds						
Command	0181h	0181h					
Parameter	Length	8 byte					
	Range	0 to 127 (00h to 7Fh)					
Status	None						
Reference	•Central values	63 (3Fh) or 64 (40h) become stop (speed 0).					
	•As the difference	ce increases with the central value, the speed increases;					
	0 (00h) or 127	(7Fh) are high speed.					
	•Zoom Sp	eed Parameter (p0, p1)					
		0 (00h): Maximum speed to Wide side					
	12'	7 (7Fh): Maximum speed to Tele side					
	•Focus Sp	eed Parameter (p2, p3)					
		0 (00h): Maximum speed to Far side					
	127	7 (7Fh): Maximum speed to Near side					
	•Tilt Speed	d Parameter (p4, p5)					
	0	(00h): Maximum speed to top side					
	127	(7Fh): Maximum speed to bottom side					
	•Pan Spee	d Parameter (p6, p7)					
	0	(00h): Maximum speed to the right side					
	127 (7Fh): Maximum speed to the left side						

# • Format of Control Code

d0		d1	d2	d3	d4	_				
Heade	er	Device	e Num	Com	mand					
FFh		30h	30h	01h	81h					
		d5	d6	d7	d8	d9	d10	d11	d12	d13
		Zoom	Speed	Focus	Focus Speed		Speed	Pan S	Speed	End mark
		Parai	neter	Para	Parameter		meter	Parar	neter	
		p0	p1	p2	р3	p4	p5	р6	р7	EFh

The zoom, focus, tilt, and pan speeds indicate in 2 digits Hexadecimal, and its								
ASCII code treats as the parameter.								
Example: Zoom Speed					p0	p1		
	100	$\Rightarrow$	64h	$\Rightarrow$	36h	34h		

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	30h e0 e1		EFh
				<u>Il</u>	

	· ·					
Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value						
Example				e0	e1	
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h	
■ In case of Busy:	$00010000B \Rightarrow$	10h	$\Rightarrow$	31h	30h	
■ In case of Parameter Err	ror: 01010000B $\Rightarrow$	50h	$\Rightarrow$	35h	30h	

	$\mathcal{E}$
Busy Error	•In case of executing <b>Shot Memory Movement</b> Command.
	•While Wiper Control and Washer Control commands are being
	executed.(Pan-tilt movement)
	•While <b>ND Filter Control</b> commands are being executed.
	(Pan-tilt movement)
Parameter Error	•Assigned parameter is an invalid value.

# 11.6 Shot Memory Recording

System Control Command Type 1

		· · · · · · · · · · · · · · · · · · ·				
Function	Record the zoo	Record the zooming/focusing positions and tilting/panning angles (position)				
	when the comn	nand is received to assigned shot memory number				
Command	0182h	0182h				
Parameter	Length	2 byte				
	Range	0 to 127 (00h to 7Fh)				
Status	None	None				
Reference	•Specify the shot memory number to be recorded by using the parameter value. (128					
	[0-127] location	ns can be registered.)				

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7
Header	Device Num		Command		Parar	End mark	
FFh	30h	30h	01h	82h	p0	p1	EFh
				- II			

The shot memory number indicates in 2 digits Hexadecimal, and its ASCII code										
treats as the p	treats as the parameter.									
Example:					p0	p1				
	4	$\Rightarrow$	04h	$\Rightarrow$	30h	34h				

# Answer Format

d0	d1	d2	d3	d4	d5
Header	Device	Num	Error	End mark	
FEh	30h	30h	e0	e1	EFh
				TI .	

Error Flag indicates in 2 digit	s Hexadecimal and 1	eturns AS	CII cod	le value	
Example				e0	e1
■ In case of No Error:	$00000000B \Rightarrow$	00h	$\Rightarrow$	30h	30h
■ In case of Parameter Error	:: 01010000B ⇒	50h	$\Rightarrow$	35h	30h

Parameter Error	•Assigned parameter is an invalid value.
I didilictor Error	Tibbighed parameter is an invalid value.

# 11.7 Shot Memory Movement

System Control Command Type 2

Function	Move to the zooming/focusing positions and tilting/panning angles (position)							
	stored for the assigned shot memory number							
Command	0183h	0183h						
Parameter	Length	4 byte						
	Range	Shot memory number: 0 to 127 (00h to 7Fh)						
		Shot movement time (seconds): 0,2 to 48 (02h to 30h)						
Status	None							
Reference	•This command is ineffective until to store preset position by <b>Shot Memory</b>							
	Recording comment.	mmand, since shot memory is unused at the factory shipping						
	assigned Shot	s command, start Pan/Tilt/Zoom/Focus operations to the Memory position at the same time, and flags <b>in operation of m/Focus</b> come out 1.						
	When each operation reaches to Shot Memory position, all of operation will stop and corresponding flags be cleared to zero.							
	•The movement is canceled and stopped by sending the command of shot movement time 0 [0h] again during the shot memory movement by this command.							

## • Format of Control Code

d0	d1	d2	d3	d4	d5	d6	d7	d8	d9
Header	Device Num		Command		Shot memory		Shot time		End
					parai	meter	parai	neter	mark
FFh	30h	30h	01h	83h	p0	p1	p2	р3	EFh

The shot memory numbers and shot movement times indicate in 2 digits Hexadecimal, and its ASCII codes treat as the parameter. Shot memory number of 5 seconds and shot movement time of Example: 20 seconds Shot memory number p0 **p**1 05h 30h 35h  $\Rightarrow$  $\Rightarrow$ Shot movement time p2 **p**3 20  $\Rightarrow$ 14h  $\Rightarrow$ 31h 34h

#### Answer Format

d0	d1	d2	d3	d4	d5
Header	Device Num		Error	End mark	
FEh	30h	30h	e0	e1	EFh
				11	

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value								
Example					e0	e1		
■ In case of No Error:	00000000B	$\Rightarrow$	00h	$\Rightarrow$	30h	30h		
■ In case of Busy:	00010000B	$\Rightarrow$	10h	$\Rightarrow$	31h	30h		
■ In case of Parameter Err	ror:01010000B	$\Rightarrow$	50h	$\Rightarrow$	35h	30h		

	$\mathcal{E}$
Busy Error	•While Camera is being initialized.
	•In case of executing Wiper Control and Washer Control
	Commands.
	•While <b>ND Filter Control</b> commands are being executed.
	•In case of executing White Balance Preset.
	•In case of executing One Shot AF.
Parameter Error	•Assigned parameter is an invalid value.

## 11.8 Serial Number Information Request

Camera Control Command Type 1

Function	Return the serial	Leturn the serial number information of pan-tilt system					
Command	01E9h						
Parameter	Length	1 byte					
	Value	0h					
Status	Length	15 byte					
	Value	Return the serial number information by ASCII code					
Reference	• For the detailed	• For the detailed relation between the status and the serial number, refer to					
	Details of Seria	Details of Serial Numbers below.					

#### • Format of Control Code

d0	d1	d2	d3	d4	d5	d6
Header	Device Num		Command		Parameter	End mark
FFh	30h	30h	01h	E9h	30h	EFh

#### Answer Format

## ■ In case of no Error

_	d0	d1	d2	d3	d4	d5		d19	d20		
	Header Device Num		- Num	Error	Code	Ser	End				
	Ticadei	Device	Device I (uiii		Elifor Code		Serial Number Information				
	FEh	30h	30h	30h	30h	s0		S14	EFh		

ASCII code of serial number is fixed as the status value. s14s12D 2D 2D

### ■ In case of Error

Example:

d0	d1	d2	d3	d4	d5	
Header	Device Num		Error	End mark		
FEh	30h	30h	e0	e1	EFh	
				111		

Error Flag indicates in 2 digits Hexadecimal and returns ASCII code value Example e0e1 ■ In case of Parameter Error:  $01010000B \Rightarrow$ 35h 50h 30h

## • Condition of Error flag to be set

Parameter Error •Assigned parameter is an invalid value.

## •Details of Serial Number (An example of XU-80W)

S0	S1	S2	<b>S</b> 3	S4	S5	S6	S7	S8	<b>S</b> 9	S10	S11	S12	S13	S14
Model Name					Proc Co	duct de	Serial Number			Rese	erve			
X	U	-	8	0	W	2	5	0	0	0	0	0	-	-
58h	55h	2Dh	38h	30h	57h	32h	35h	30h	30h	30h	30h	30h	2Dh	2Dh

Note: The values above is an example and it is varies in each equipment.

# 12. Command Table

1<sup>st</sup> byte:01h 2<sup>nd</sup> byte: See below.

Note: Do not use commands of "Reserve". These are used for system and doing so may cause malfunction.

Higher Lower	0xh	1xh	2xh	3xh	4xh	5xh	6xh	7xh
x0h						Pan Speed Specification		
x1h						Tilt Speed Specification		AUX control
x2h						Pan/Tilt Speed Request	Pan/Tilt Angle Assignment	
x3h						Pan/Tilt Operation	Pan/Tilt Angle Request	
x4h								Reserve
x5h								
x6h								
x7h								
x8h						Initialization		
x9h						Pan/Tilt Speed Request		
xAh								Wiper Control
xBh						Pan/Tilt Factor Request		Tally Control
xCh						Pan-Tilt Angle Range		
xDh								
xEh								
xFh								

Higher Lower	8xh	9xh	Axh	Bxh	Cxh	Dxh	Exh	Fxh
x0h		Reserve	Camera Power Control			Reserve		Reserve
x1h	ZFTP Speed Control	Reserve	Focus Control			Reserve	Color Adjustment Control	Reserve
x2h	Shot Memory	Reserve	Zoom Control			Reserve	Reserve	Gamma Specification
x3h	Shot Operation		Zoom Position Assignment		Iris Request	Reserve	AE Level Correction	Reserve
x4h	Shooting Mode Switching		Zoom Position Request	Zoom Speed		Reserve	GENLOCK Phase Relative Value Control	Reserve
x5h			WDR Control	Reserve	Reserve		Reserve	Reserve
x6h	Status Request		Iris Assignment	ND Filter Control	Camera Status		Reserve	
x7h	Model Name Request		AWB Control		Reserve		GENLOCK Phase Absolute Value Control	
x8h	ROM Version Request		Shutter Control	Color Bar Control			Reserve	
x9h							Reserve	
xAh				Auto IR Control		Digital Zoom Magnification	AUX Fan Status	
xBh				IR Filter Control			Reserve	
xCh								
xDh		Shutter Detail Settings	Shutter Assignment	Camera Setting				
xEh		Gain Detail Settings	Gain Assignment	Camera Version Request				
xFh		Reserve						